



Installation and Setup Guide

Sun[™] Studio 8

Sun Microsystems, Inc.
www.sun.com

Part No. 817-5074-10
March 2004, Revision A

Submit comments about this document at: <http://www.sun.com/hwdocs/feedback>

Copyright © 2004 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, U.S.A. All rights reserved.

U.S. Government Rights - Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements. Use is subject to license terms.

This distribution may include materials developed by third parties.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and in other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, Java, and JavaHelp are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon architecture developed by Sun Microsystems, Inc.

This product is covered and controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright © 2004 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, Etats-Unis. Tous droits réservés.

L'utilisation est soumise aux termes de la Licence.

Cette distribution peut comprendre des composants développés par des tierces parties.

Des parties de ce produit pourront être dérivées des systèmes Berkeley BSD licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, Java, et JavaHelp sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc.

Ce produit est soumis à la législation américaine en matière de contrôle des exportations et peut être soumis à la réglementation en vigueur dans d'autres pays dans le domaine des exportations et importations. Les utilisations, ou utilisateurs finaux, pour des armes nucléaires, des missiles, des armes biologiques et chimiques ou du nucléaire maritime, directement ou indirectement, sont strictement interdites. Les exportations ou réexportations vers les pays sous embargo américain, ou vers des entités figurant sur les listes d'exclusion d'exportation américaines, y compris, mais de manière non exhaustive, la liste de personnes qui font objet d'un ordre de ne pas participer, d'une façon directe ou indirecte, aux exportations des produits ou des services qui sont régis par la législation américaine en matière de contrôle des exportations et la liste de ressortissants spécifiquement désignés, sont rigoureusement interdites.

LA DOCUMENTATION EST FOURNIE "EN L'ÉTAT" ET TOUTES AUTRES CONDITIONS, DECLARATIONS ET GARANTIES EXPRESSES OU TACITES SONT FORMELLEMENT EXCLUES, DANS LA MESURE AUTORISEE PAR LA LOI APPLICABLE, Y COMPRIS NOTAMMENT TOUTE GARANTIE IMPLICITE RELATIVE A LA QUALITE MARCHANDE, A L'APTITUDE A UNE UTILISATION PARTICULIERE OU A L'ABSENCE DE CONTREFAÇON.



Contents

Before You Begin 9

Typographic Conventions 9

Shell Prompts 10

Accessing Compilers and Tools Documentation 11

Documentation in Accessible Formats 12

Related Compilers and Tools Documentation 12

Accessing Related Solaris Documentation 13

Resources for Developers 13

Contacting Sun Technical Support 14

Sun Welcomes Your Comments 14

1. Preparing for Installation 15

Software Installation Overview 16

System Requirements 17

Adding Swap Space 18

Choosing Local Display or Remote Display of the Installer 19

Preparing to Install Using a Remote Display 19

Preparing to Install Using a Remote Display With an NFS-Mounted
Filesystem 20

Locating the Product Serial Number 21

Installing from Electronic Download Files	21
Features Included in This Release	24
2. Installing Sun Studio 8 Software	25
Supporting Previous Sun ONE Studio and Forte Developer Releases	26
Upgrading From Try and Buy Software	27
Choosing an Installation Method	27
Using the Graphical User Interface Installer	28
Using the Command-Line Installer	32
Using the Batch Installer	34
Using the Solaris JumpStart Installer	36
Installing the J2SE Platform and Related Solaris Operating System Patches	37
Verifying a Successful Installation	38
Setting Up Access to the Developer Tools and Man Pages	38
3. Starting and Setting Up the Sun Studio 8 IDE	43
Starting the IDE	43
Using the Setup Wizard	44
Using the Registration Wizard	44
Note To System Administrators	45
4. Uninstalling Sun Studio 8 Software	47
Uninstalling When Previous Versions Of Sun ONE Studio Are Installed	48
Choosing Local Display or Remote Display of an Uninstaller	48
Preparing to Uninstall Using a Remote Display	48
Using the Batch Software Uninstaller	49
Using a Graphical User Interface Uninstaller	50
Using a Command-Line Uninstaller	52
Using the Solaris Product Registry Software Uninstaller	53

5. Troubleshooting 55

Installing in a Directory That Is Reached by a Symbolic Link 55

Product Registry Problems 56

How Do I Identify and Fix a Failed Installation? 57

How Do I Fix a Failed Uninstallation? 57

What Can I Do If the `productregistry` File Is Corrupted? 58

Log Files and Serial Number Files 59

How Can I View the Installation Log Files? 59

How Do I Find the Installed Serial Number? 60

What Can I Do If I Lose My Serial Number? 60

Installing With a Remote Display Installation 60

What If the Installation Fails on an NFS-Mounted Filesystem? 61

How Do I Initialize a ToolTalk Software Session During Remote Display Installation? 61

What Can I Do If the Batch Installer Stalls? 62

Workaround for Sun Studio Installation on the Solaris 7 OS 63

A. Sun Studio 8 Components and Packages 65

B. Patch Identification Numbers and Descriptions 77

C. J2SE Technology Required Patch Identification Numbers and Descriptions 81

D. Version Numbers of Sun Studio 8 Software Components 85

Glossary 87

Index 89

Tables

TABLE P-1	Typeface Conventions	9
TABLE P-2	Code Conventions	10
TABLE 1-1	System Requirements	17
TABLE 2-1	Sun Studio 8 Installation Location When Previous Releases Are Installed.	26
TABLE 2-2	<code>batch_installer</code> Options and Option Descriptions	35
TABLE 2-3	Installation Scenarios Using the <code>batch_installer</code> Command and Options	35
TABLE 4-1	Software Names and Related Uninstaller <code>.class</code> File Names	50
TABLE A-1	Sun Studio 8 Product Metacluster Components and Packages for Solaris <i>SPARC Platform Edition</i>	66
TABLE A-2	Sun Studio 8 Product Metacluster Components and Packages for Solaris <i>x86 Platform Edition</i>	72
TABLE B-1	Patches Installed With Sun Studio 8 Software for Solaris 7 <i>SPARC Platform Edition</i>	77
TABLE B-2	Patches Installed With Sun Studio 8 Software for Solaris 7 <i>x86 Platform Edition</i>	78
TABLE B-3	Patches Installed With Sun Studio 8 Software for Solaris 8 <i>SPARC Platform Edition</i>	78
TABLE B-4	Patches Installed With Sun Studio 8 Software for Solaris 8 <i>x86 Platform Edition</i>	78
TABLE B-5	Patches Installed With Sun Studio 8 Software for Solaris 9 <i>SPARC Platform Edition</i>	78
TABLE B-6	Patches Installed With Sun Studio 8 Software for Solaris 9 <i>x86 Platform Edition</i>	79
TABLE C-1	Patches Installed With the J2SE Technology for Solaris 7 <i>SPARC Platform Edition</i>	81
TABLE C-2	Patches Installed With the J2SE Technology for Solaris 7 <i>x86 Platform Edition</i>	82
TABLE C-3	Patches Installed With the J2SE Technology for Solaris 8 <i>SPARC Platform Edition</i>	83
TABLE C-4	Patches Installed With the J2SE Technology for Solaris 8 <i>x86 Platform Edition</i>	83

TABLE C-5	Patches Installed With the J2SE Technology for Solaris 9 <i>SPARC Platform Edition</i>	84
TABLE C-6	Patches Installed With the J2SE Technology for Solaris 9 <i>x86 Platform Edition</i>	84
TABLE D-1	Version Numbers of Components of Sun Studio 8 Software	85

Before You Begin

This installation guide gives instructions for how to perform the following tasks:

- Install the Sun™ Studio 8 software and serial number
- Install the recommended Java™ 2 Platform, Standard Edition (J2SE™) technology
- Uninstall Sun Studio 8 product software
- Troubleshoot installation problems
- Run the Integrated Development Environment (IDE) after it is installed

This book is designed for system administrators who install software and for developers who use software development applications. Experience with the Solaris™ Operating System (OS) and UNIX® commands is required.

Typographic Conventions

TABLE P-1 Typeface Conventions

Typeface	Meaning	Examples
AaBbCc123	The names of commands, files, and directories; on-screen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>% You have mail.</code>
AaBbCc123	What you type, when contrasted with on-screen computer output	<code>% su</code> Password:
<i>AaBbCc123</i>	Book titles, new words or terms, words to be emphasized	Read Chapter 6 in the <i>User's Guide</i> . These are called <i>class</i> options. You <i>must</i> be superuser to do this.
<i>AaBbCc123</i>	Command-line placeholder text; replace with a real name or value	To delete a file, type rm <i>filename</i> .

TABLE P-2 Code Conventions

Code Symbol	Meaning	Notation	Code Example
[]	Brackets contain arguments that are optional.	<i>O</i> [<i>n</i>]	<i>O</i> 4, <i>O</i>
{ }	Braces contain a set of choices for a required option.	<i>d</i> { <i>y</i> <i>n</i> }	<i>d</i> y
	The “pipe” or “bar” symbol separates arguments, only one of which may be chosen.	<i>B</i> { <i>dynamic</i> <i>static</i> }	<i>B</i> static
:	The colon, like the comma, is sometimes used to separate arguments.	<i>Rdir</i> [: <i>dir</i>]	<i>R</i> /local/libs:/U/a
...	The ellipsis indicates omission in a series.	<i>xinline</i> = <i>f1</i> [,... <i>fn</i>]	<i>xinline</i> =alpha,dos

Shell Prompts

Shell	Prompt
C shell	<i>machine-name</i> %
C shell superuser	<i>machine-name</i> #
Bourne shell and Korn shell	\$
Superuser for Bourne shell and Korn shell	#

Accessing Compilers and Tools Documentation

You can access the documentation at the following locations:

- The documentation is available from the documentation index that is installed with the software on your local system or network at `file:/opt/SUNWspro/docs/index.html`.

If your software is not installed in the `/opt` directory, ask your system administrator for the equivalent path on your system.

- Most manuals are available from the `docs.sun.com`sm web site. The following titles are available through your installed software only:
 - *Standard C++ Library Class Reference*
 - *Standard C++ Library User's Guide*
 - *Tools.h++ Class Library Reference*
 - *Tools.h++ User's Guide*
- The release notes are available from the `docs.sun.com` web site.
- Online help for all components of the IDE is available through the Help menu, as well as through Help buttons on many windows and dialogs, in the IDE.

The `docs.sun.com` web site (<http://docs.sun.com>) enables you to read, print, and buy Sun Microsystems manuals through the Internet. If you cannot find a manual, see the documentation index that is installed with the software on your local system or network.

Note – Sun is not responsible for the availability of third-party web sites mentioned in this document and does not endorse and is not responsible or liable for any content, advertising, products, or other materials on or available from such sites or resources. Sun will not be responsible or liable for any damage or loss caused or alleged to be caused by or in connection with use of or reliance on any such content, goods, or services available on or through any such sites or resources.

Documentation in Accessible Formats

The documentation is provided in accessible formats that are readable by assistive technologies for users with disabilities. You can find accessible versions of documentation as described in the following table. If your software is not installed in the `/opt` directory, ask your system administrator for the equivalent path on your system.

Type of Documentation	Format and Location of Accessible Version
Manuals (except third-party manuals)	HTML at http://docs.sun.com
Third-party manuals: • <i>Standard C++ Library Class Reference</i> • <i>Standard C++ Library User's Guide</i> • <i>Tools.h++ Class Library Reference</i> • <i>Tools.h++ User's Guide</i>	HTML in the installed software through the documentation index at <code>file:/opt/SUNWspro/docs/index.html</code>
Readmes and man pages	HTML in the installed software through the documentation index at <code>file:/opt/SUNWspro/docs/index.html</code>
Online help	HTML available through the Help menu in the IDE
Release notes	HTML at http://docs.sun.com

Related Compilers and Tools Documentation

The following table describes related documentation that is available at `file:/opt/SUNWspro/docs/index.html` and <http://docs.sun.com>. If your software is not installed in the `/opt` directory, ask your system administrator for the equivalent path on your system.

Document Title	Description
<i>Numerical Computation Guide</i>	Describes issues regarding the numerical accuracy of floating-point computations.

Accessing Related Solaris Documentation

The following table describes related documentation that is available through the `docs.sun.com` web site. The following table describes related documentation that is available through the `docs.sun.com` web site.

Document Collection	Document Title	Description
Solaris Reference Manual Collection	See the titles of man page sections.	Provides information about the Solaris Operating System.
Solaris Software Developer Collection	<i>Linker and Libraries Guide</i>	Describes the operations of the Solaris link-editor and runtime linker.
Solaris Software Developer Collection	<i>Multithreaded Programming Guide</i>	Covers the POSIX and Solaris threads APIs, programming with synchronization objects, compiling multithreaded programs, and finding tools for multithreaded programs.

Resources for Developers

Visit <http://developers.sun.com/prodtech/cc> to find these frequently updated resources:

- Articles on programming techniques and best practices
- A knowledge base of short programming tips
- Documentation of compilers and tools components, as well as corrections to the documentation that is installed with your software
- Information on support levels
- User forums
- Downloadable code samples
- New technology previews

You can find additional resources for developers at <http://developers.sun.com>.

Contacting Sun Technical Support

If you have technical questions about this product that are not answered in this document, go to:

<http://www.sun.com/service/contacting>

Sun Welcomes Your Comments

Sun is interested in improving its documentation and welcomes your comments and suggestions. Email your comments to Sun at this address:

`docfeedback@sun.com`

Please include the part number (817-5074-10) of the document in the subject line of your email.

Preparing for Installation

This chapter includes information about the following topics:

- The software installation overview
- System requirements
- Adding swap space
- Choosing local display or remote display of the installer

Software Installation Overview

The following steps outline the general process you follow to install the Sun Studio 8 software, product serial number, and supporting software. See the references provided in each step for specific procedures.

Task	Description	For Instructions
1. Verify that the system on which you are installing the Sun Studio 8 software meets the minimum requirements for this release.	Using a system that meets the system requirements is recommended for proper performance.	See “System Requirements” on page 17 .
2. Determine whether you want to keep your previous version of the Sun ONE Studio or Forte Developer software.	Install Sun Studio 8 in the same directory as Sun ONE Studio 8, Compiler Collection. For other previous release, identify a different directory in which to install this Sun Studio 8 software.	See “Supporting Previous Sun ONE Studio and Forte Developer Releases” on page 26 of Chapter 2 .
3. You must install the product serial number during product installation.	The product does not work without a valid serial number.	See Chapter 2 for product installation and serial number installation.
4. Determine whether you are going to display the installer locally or remotely.	You can install the Sun Studio software using a remote display or local display.	Refer to “Choosing Local Display or Remote Display of the Installer” on page 19 for more details.
5. Verify the Java™ 2 Platform, Standard Edition technology installed on your system.	The Sun Studio 8 software supports the Java™ 2 Platform, Standard Edition 1.4.2_02 technology	See Chapter 2 for J2SE installation instructions.

After following the instructions in this manual, you are ready to use your Sun Studio 8 software.

System Requirements

This Sun Studio 8 release supports the Solaris™ operating system (*SPARC® Platform Edition*) versions 7, 8, and 9; and the Solaris operating system (*x86 Platform Edition*) versions 7, 8, and 9.

Note – For further disk space requirements and important last minute information about this release, see the release notes for the Sun Studio 8 software on the product web site at <http://www.sun.com/software/products/studio/index.html>.

TABLE 1-1 lists the system requirements.

TABLE 1-1 System Requirements

	Solaris <i>SPARC Platform Edition</i>	Solaris <i>x86 Platform Edition</i>
Operating system	Solaris 7, 8, or 9	Solaris 7, 8, or 9
System	Recommended: Sun Blade 750 MHz or UltraSPARC III 750 MHz Minimum: Ultra 60 450 MHz	Recommended: Pentium III 1 GHz Minimum: Pentium III 500 MHz
Disk Space	1.5 Gbytes	500 Mbytes
(Use the <code>df -k</code> command to check your disk space.)		
Monitor	1024 x 768 resolution	
Memory	1 Gbyte recommended; 512 Mbytes minimum	
Swap Space*	2 Gbytes recommended; 1 Gbytes minimum	
J2SE Technology	J2SE 1.4.2_02 technology	
Operating System Configurations	Entire Solaris Software Group Plus OEM Support, Entire Solaris Software Group, or Developer Solaris Software Group (To determine your operating system configuration, you need to verify the installed packages. Specific packages are installed for each configuration. See the Solaris OS installation documentation for more details.)	

*Use the `swap -s` command to check the swap space.

Adding Swap Space

If you want to add swap space, do the following:

1. Become a superuser (root) by typing:

```
% su  
Password: root-password
```

2. Create a file in a selected directory to add swap space by typing:

```
mkfile number [m|k|b] /directory/swap-file-name
```

where *number* is an amount of swap space, followed by either **m** for megabyte, **k** for kilobyte, or **b** for block. The *directory* is a directory in which you have permission to add swap space. The *swap-file-name* is the name of the swap file you are creating.

For example, to create a 16-megabyte swap file named `16mswap` in the `foo` directory, type the following:

```
# mkfile 16m /foo/16mswap
```

See the `mkfile(1M)` man page for more information.

3. Verify that the file was created by typing:

```
# ls -l /directory/swap-file-name
```

The new file appears in the directory. For example:

```
# ls -l /foo/16mswap  
-rw-----T  1 root    other    16777216 Dec 12 14:24 /foo/16mswap
```

4. Run the `swap` command to specify the additional swap space by typing:

```
# swap -a /directory/swap-file-name
```

5. Verify that the extra swap space was added by typing:

```
#swap -s
```

The output shows the allocated swap space. For example:

```
#swap -s
total: 289336k bytes allocated + 27008k reserved = 316344k used,
298336k available
```

Choosing Local Display or Remote Display of the Installer

You can display the installer either locally or remotely while you are installing the Sun Studio 8 software with the graphical user interface installer or the command-line installer:

- **Local display.** The source computer and the display computer are the same computer. The installer window or command-line installer is displayed on the same computer that contains the product CD-ROM or downloaded files and runs the installer. Continue to [Chapter 2](#).
- **Remote display.** The source computer and the display computer are different computers. The source computer contains the product CD-ROM or downloaded files and runs the installer. The display computer displays the installer window or command-line installer. To install using a remote display, follow the instructions in [“Preparing to Install Using a Remote Display” on page 19](#) or [“Preparing to Install Using a Remote Display With an NFS-Mounted Filesystem” on page 20](#).

Preparing to Install Using a Remote Display

To prepare for installation using a remote display, follow these steps:

1. On the display computer, enable client access to the X server by typing the following at a command line:

```
% xhost + source-computer-name
```

Replace *source-computer-name* with the output of the `/usr/bin/hostname` command entered on the source computer, which is the computer that contains the product CD-ROM or downloaded files.

2. Log in to the source computer and become a superuser (root) by typing:

```
% rlogin source-computer-name -l rootname  
Password: root-password
```

3. On the source computer, set the display to the monitor that is attached to the display computer.

If you use the C shell, type:

```
# setenv DISPLAY display-computer-name:0.0
```

If you use the Bourne shell, type:

```
# DISPLAY=display-computer-name:0.0  
# export DISPLAY
```

If you use the Korn shell, type:

```
# export DISPLAY=display-computer-name:0.0
```

Replace *display-computer-name* with the output of the `/usr/bin/hostname` command entered on the display computer.

Preparing to Install Using a Remote Display With an NFS-Mounted Filesystem

You can install using a remote display if you have write permission on the NFS-mounted filesystem. See [“What If the Installation Fails on an NFS-Mounted Filesystem?”](#) on page 61 of [Chapter 5](#) for troubleshooting information.

Note – If you choose to install with this method, all of the files will be owned by nobody on the NFS-mounted filesystem, which makes it difficult to know who owns the directory. Also note that the uninstaller will reside on your local machine, so you must use that local machine to run the uninstaller if you choose to uninstall the product.

Follow the steps below to prepare for installation using a remote display with an NFS-mounted filesystem.

Locating the Product Serial Number

When you purchase the product, the serial number is listed on a card that is enclosed in the product package. The 26-character number on the card is the number that you enter in the Enter Serial Number page of the installer during installation. You can also generate a 60-day trial serial number during the installation process.

Installing from Electronic Download Files

If you obtained your files through electronic download, you can find complete instructions for downloading and extracting the downloaded files on the download page of the product web site at

<http://www.sun.com/software/products/studio/index.html>. Follow the instructions in the *Download Instructions* before you proceed with product installation.

Preparing the Source Computer

1. Become a superuser (root) by typing:

```
% su
Password: root-password
```

Note – In the following examples, the CD-ROM name `studio_8_sol_sparc` is used. Use the name of your product CD-ROM in place of `studio_8_sol_sparc`. If you have electronically downloaded the product files, use the download directory name in place of `studio_8_sol_sparc`. If you are installing from electronically downloaded files, all files must be untarred in the *source-machine/download-directory* before proceeding with installation.

2. Add the following line to your `/etc/dfs/dfstab` file in order to share the product image as an NFS filesystem:

```
share -F nfs -o ro /cdrom/studio_8_sol_sparc
```

3. Verify that your source computer is an NFS server by typing:

```
# ps -ef | grep nfsd
```

If screen output that resembles the following example appears, then `nfsd` is running:

```
root 237 1 17 Jun 04 ? 0:00 /usr/lib/nfs/nfsd -a 16
```

If you do not see screen output like the preceding example, start `nfsd` by typing:

```
# /etc/init.d/nfs.server start
# ps -ef | grep nfsd
```

You should see screen output similar to the previous example. If not, contact your system administrator or your Sun authorized service provider.

If `nfsd` is running, to make the product image available, type:

```
# /usr/sbin/shareall
```

4. Ensure that your source computer is exporting your product directory by typing:

```
# /usr/sbin/dfshares
```

Screen output that resembles the following example appears:

RESOURCE	SERVER	ACCESS	TRANSPORT
server-name:product-location	server-name	-	-

Preparing the Display Computer

1. Enable client access to the X server by typing the following at a command line:

```
% /usr/openwin/bin/xhost + source-machine-name
```

Replace *source-computer-name* with the output of the `/usr/bin/hostname` command entered on the source computer.

2. Log in as superuser (root) by typing:

```
% su  
Password: root-password
```

3. Create a new directory by typing:

```
# mkdir /install-directory
```

where *install-directory* is the directory in which you want to install the product.

4. Mount the product files by typing:

```
# mount source-machine:/cdrom/studio_8_sol_sparc /install-directory
```

5. Go to the directory that you created in [Step 3](#) by typing:

```
# cd /install-directory
```

6. Set the display to the monitor you are using.

If you use the C shell, type:

```
# setenv DISPLAY source-computer-name:0.0
```

If you use the Bourne shell, type:

```
# DISPLAY=source-computer-name:0.0  
# export DISPLAY
```

If you use the Korn shell, type:

```
# export DISPLAY=source-computer-name:0.0
```

Features Included in This Release

This Sun Studio 8 software release includes the following installation features:

- Graphical user interface installation
- Command-line installation
- Batch installation
- Solaris JumpStart™ installation (for the Solaris™ 9 operating system only)
- Serial number installation tool (snit)
- J2SE software installation
- Graphical user interface uninstallation
- Command-line uninstallation
- Batch uninstallation

This document includes instructions for using each of the features.

Installing Sun Studio 8 Software

This chapter gives you instructions for installing your Sun™ Studio 8 software and serial number.

Note – Do not use the `pkgadd` command to install the software. Use the provided installer.

Supporting Previous Sun ONE Studio and Forte Developer Releases

[TABLE 2-1](#) describes how you can determine where to install Sun Studio 8 software if previous releases are installed on your system.

TABLE 2-1 Sun Studio 8 Installation Location When Previous Releases Are Installed.

Software version installed	Location in which to install Sun Studio 8 software
Sun Studio 8 Early Access software	The product install automatically uninstalls any Early Access version during the installation process. If you choose to manually uninstall the Early Access version from your system, then see “Uninstalling When Previous Versions Of Sun ONE Studio Are Installed” on page 48 for instructions.
Sun ONE Studio 8, Compiler Collection software	Option 1: Install Sun Studio 8 in the same directory as Sun ONE Studio 8, Compiler Collection. This option allows you to keep the existing Sun ONE Studio 8, Compiler Collection patches and upgrades. If you choose this option and need to uninstall Sun Studio 8, you also uninstall Sun ONE Studio 8, Compiler Collection. Option 2: Install Sun Studio 8 separately from Sun ONE Studio 8, Compiler Collection. If you choose this option, then you have to install Sun Studio 8 software on a different system from Sun ONE Studio 8, Compiler Collection. You need to install any Sun ONE Studio 8, Compiler Collection patches with the Sun Studio 8 installation. You can obtain the patches from http://sunsolve.sun.com .
Sun ONE Studio 7, Compiler Collection	Select a different installation directory for the new release. For example, if you previously installed development tools in the /opt directory, install the new development tools in a new directory on a filesystem with sufficient disk space. If you install more than one release in the same directory, the uninstaller might remove packages from the release that you do not want to uninstall, and you might corrupt the product registry file.
Forte Developer releases	Select a different installation directory for the new release. For example, if you previously installed development tools in the /opt directory, install the new development tools in a new directory on a filesystem with sufficient disk space. If you install more than one release in the same directory, the uninstaller might remove packages from the release that you do not want to uninstall, and you might corrupt the product registry file.

After installation, modify your PATH and MANPATH environment variables to include the new directory. See [“Setting Up Access to the Developer Tools and Man Pages” on page 38](#) for more information about setting the variables to use the new release.

Upgrading From Try and Buy Software

When you upgrade from Try and Buy software to purchased software, you do not need to reinstall the software product. You only need to install your permanent serial number. The Serial Number Installation Tool (snit) is a utility that works from the command line and is used to display the contents of a license file and to install serial numbers into the license file.

Follow the steps below to install your permanent serial number.

1. **Locate the permanent serial number.** See “Locating the Product Serial Number” on page 21.
2. **Become a superuser (root) by typing:**

```
% su
Password: root-password
```

3. **Use the `snit` command to enter your serial number by typing:**

```
% /install-directory/SUNWsprd/bin/snit -i serial-number -f /install-
directory/SUNWsprd/prod/lib/serial.dat
```

The serial number is installed in the `serial.dat` file of your product. Refer to the `snit(1)` man page for more details about the `snit` command options.

Choosing an Installation Method

There are four ways to install the Sun Studio 8 software:

- Use the graphical user interface (GUI) installer. See “Using the Graphical User Interface Installer” on page 28 for instructions.
- Use the command-line installer if you do not have graphical user interface capabilities. See “Using the Command-Line Installer” on page 32 for instructions.
- Use the batch installer (see “Using the Batch Installer” on page 34) to install the software in a default installation.

- Use the Solaris JumpStart™ installer on the Solaris™ 9 Operating System (OS) (see [“Using the Solaris JumpStart Installer” on page 36](#)). Using the installer automates the software installation process if you need to install the Sun Studio 8 software on multiple systems.

Note – If you are using Solaris OS 7, you need to run the installer using the `-j` option with the following syntax: `./installer -jdkhome /usr/j2se` so the installer can find the required J2SE 1.2 software.

Note – The CD-ROM names are `studio_8_sol_sparc` and `studio_8_sol_x86`. In the examples provided, the CD-ROM name `studio_8_sol_arch` is used.

Using the Graphical User Interface Installer

These instructions describe how to install the Sun Studio 8 software and serial number using the graphical user interface installer available on the product CD-ROM. If you get the product from an electronic download, be sure to follow all instructions in the Download Instructions, which is available for download from the product web site download page.

Note – Do not use the `pkgadd` command to install the software. Use the provided installer. Do not run the installer in the background.

1. Decide if you want to install using a remote display. See [“Choosing Local Display or Remote Display of the Installer” on page 19](#) for details.
2. If you are not currently superuser (root), become a superuser by typing:

```
% su
Password: root-password
```

Note – The installer prompts you to log in as superuser (root) if you invoke the installer when you are not logged in as superuser (root).

3. Insert the CD-ROM in the CD-ROM drive.

The product installer starts.

If the installer does not start or you are using the Solaris™ 9 operating environment, the autorun feature might be disabled or unsupported on your system. In this case, use one of the following methods to start the installer:

- In the File Manager window, double-click the installer icon to start the installer.
- Invoke the installer by typing:

```
# /cdrom/studio_8_sol_arch/installer
```

The Welcome page opens.

Note – This is a multilanguage CD-ROM. If the operating system does not recognize the correct language, use the `-locales` option with `en` for English, `zh` for Simplified Chinese, or `ja` for Japanese when you invoke the installer. For example:
`/cdrom/studio_8_sol_arch/installer -locales en`

(Optional for electronic download) If you downloaded the product files from the product web site, do the following:

- a. See the *Download Instructions* available on the product web site download page for more information on extracting the tar files and using the installer launch script.
- b. From the download directory, start the installer by typing:

```
# ./installer
```

The Welcome page opens.

(Optional for using the Solaris Product Registry tool) You can start the installer by using the Solaris Product Registry tool.

- a. To start the Product Registry tool, type:

```
# prodreg
```

- b. Click New Install.

- c. In the Select Installer dialog, navigate to the download directory or `cdrom` directory, and select `installer`.

d. Click OK, and the installer starts.

The Welcome page opens.

4. Click Next in the Welcome page.

The Initializing page appears, and when initialization is complete, the Binary Code License Agreement page appears.

5. In the Binary Code License Agreement page, click Accept.

If you choose Decline, you cannot continue with the installation.

6. Click Next to proceed to the Select Component page.

7. In the Select Component page, select the type of installation you want for each product.

- If you select Do Not Install, the product is not installed.
- If you select Default Install, the installer installs all components of the product and all online documentation that is associated with the components.
- If you select Custom Install, the installer allows you to select (in [Step 10](#)) which subcomponents of the product you want to install.

Note – If you select Default Install for Solaris patches, the installer installs all of the required patches for the Sun Studio 8 software, which are listed in Appendix B. If you have previously installed these patches, installing the required patches does not downgrade your system.

8. Click Next to proceed to the Select Install Directory page.

9. Decide whether you want to change the software installation directory from /opt.

See [“Supporting Previous Sun ONE Studio and Forte Developer Releases” on page 26](#) if you want to install this new Sun Studio release on a computer that contains previous Sun ONE Studio releases or Forte Developer releases.

- If you want to install in the /opt directory on the source computer, click Next. If you have installed a previous release of Sun ONE Studio software or Forte Developer software in the /opt directory on the source computer, you must choose a different installation directory.
- If you want to install the software in a directory other than the /opt directory on the source computer, type the new location in the text field or browse for another location. If you do not have permission to write to the directory you select, the installer asks you if you want to change permissions. You must have write permission for the selected directory before you can proceed with installation. See the `chmod(1)` man page for information on changing directory permissions.

10. Click Next when you have entered the installation directory.

If you did not select Custom Install for any of the products, skip to [Step 11](#).

(Optional for Custom Install) If you selected Custom Install for any of the products in the Product Selection page, a Subcomponent Selection page is displayed for each of those products.

a. Select the subcomponents you want to install by clicking the check box next to the item.

Items with a check mark in the box will be installed.

b. Click Next to continue with installation.

11. In the Enter Serial Number page, click the 60-day Trial Serial Number button to generate the 60-day trial serial number or enter your permanent serial number in the text box. See “Locating the Product Serial Number” on page 21 for information on finding the serial number.

12. Click Next to install the serial number.

The installer checks for adequate disk space, and the Ready to Install page appears.

13. Verify that the disk space shown at the top of the Ready to Install page is available on your system by using the `df -k` command. If you receive a disk space error message and you have sufficient disk space to install the product, then ignore the error message and continue with installation.

14. In the Ready to Install page, confirm that the items you want to install are listed.

- If the products you want are listed, click Install Now.
- If you want to install more products, click Back to return to the Select Components page, make your selections, and click Next to return to the Ready to Install page.

The Installing page appears with a progress indicator. When installation is complete, the Installation Summary page appears.

15. If you want to view the installation log file for a product, click the Details button for that product in the Installation Summary page.

16. In the After Installation Page, read the messages for information about registering the product.

17. Click Exit to finish the Sun Studio 8 software installation.

18. Remove the CD-ROM from the CD-ROM drive.

19. (Optional) If you performed the installation using a remote display, on the display computer, disable client access by typing the following:

```
# xhost - source-computer-name
```

20. Exit from superuser privileges on the source computer by typing:

```
# exit
```

21. To set up your access to the Sun Studio 8 software tools and man pages, set your `PATH` and `MANPATH` variables by following the steps in [“Setting Up Access to the Developer Tools and Man Pages” on page 38](#).

Using the Command-Line Installer

These instructions describe how to install the Sun Studio 8 software and serial number using the command-line interface.

Note – Do not use the `pkgadd` command to install the software. Use the provided installer. Do not run the installer in the background.

1. Decide if you want to install using a remote display. See [“Choosing Local Display or Remote Display of the Installer” on page 19](#) for details.
2. If you are not currently superuser, become a superuser (root) by typing:

```
% su
Password: root-password
```

Note – The installer prompts you to log in as superuser (root) if you invoke the installer when you are not logged in as superuser (root).

3. Insert the CD-ROM in the CD-ROM drive.

If the GUI installer starts, choose Exit to exit from the installer. To restart the installer in the command line, type:

```
# /cdrom/studio_8_sol_sparc/installer -nodisplay
```

Note – This is a multilanguage CD-ROM. If the operating system does not recognize the correct language, use the `-locales` option with `en` for English, `zh` for Simplified Chinese, or `ja` for Japanese when you invoke the installer. For example:

```
/cdrom/studio_8_sol_sparc/installer -nodisplay -locales en
```

(Optional for electronic download) If you downloaded the product files from the product web site, do the following:

- a. See the *Download Instructions* available on the product web site download page for more information on extracting the tar files and using the installer launch script.
- b. From the download directory, start the command-line installation by typing:

```
# /download-directory/installer -nodisplay
```

Do not run the installer in the background.

4. The installer welcomes you. Press Enter to continue.

The Binary Code License Agreement text appears.

Note – The Enter key is equivalent to the Return key on some keyboards. Press the Enter key to accept the default selections during installation.

5. Follow the installer instructions to complete the installation. See [Step 9 in “Using the Graphical User Interface Installer” on page 28](#) for additional information about selecting the installation directory.
6. When installation is complete, you can view a product’s log file by typing the number that corresponds to that product. When you finish viewing the log files, type the number that corresponds to *Done*.
7. Remove the CD-ROM from the CD-ROM drive.
8. (Optional) If you performed the installation using a remote display, on the display computer, disable client access by typing the following:

```
# xhost - source-computer-name
```

9. Exit from superuser privileges on the source computer by typing:

```
# exit
```

10. To set up your access to the Sun Studio 8 software tools and man pages, set your `PATH` and `MANPATH` variables by following the steps in [“Setting Up Access to the Developer Tools and Man Pages”](#) on page 38.

Using the Batch Installer

You can install the Sun Studio 8 software, Sun Performance Library™ software, or Sun Studio Source Distribution software with the batch installer for a default installation.

Note – Do not use the `pkgadd` command to install the software. Use the provided installer. Do not run the installer in the background.

Follow these instructions for batch installation:

1. Decide if you want to install using a remote display. See [“Choosing Local Display or Remote Display of the Installer”](#) on page 19 for details.
2. If you are not currently superuser, become a superuser (root) by typing:

```
% su
Password: root-password
```

3. Use the following command to run the batch installer:

```
batch_installer [-s serial number] [-d dirname | -R root-path] [-h]
```

(Optional for electronic download) Use the following command to run the batch installer:

```
batch_installer_component-name [-s serial number] [-d dirname | -R root-path] [-h]
```

The batch installer commands for each component are the following:

- `batch_installer_studio` for the Sun Studio compilers, tools, and IDE
- `batch_installer_perflib` for the Sun Performance Library software
- `batch_installer_src` for the Sun Studio Source Distribution software

See [TABLE 2-2](#) for the options that are available for the `batch_installer` command.

TABLE 2-2 `batch_installer` Options and Option Descriptions

Option Name	Option Description
<code>-s serial number</code>	Installs the permanent serial number. Without this option, a 60-day trial serial number is generated by default.
<code>-d dirname</code>	Installs in directory <i>dirname</i> .
<code>-R root-path</code>	Specifies the absolute path for the root system and product. Use this option in JumpStart installation to set the root directory. NOTE: Use this option only with the batch installer.
<code>-h</code>	Displays usage information for the <code>batch_installer</code> command.

The `batch_installer` command and the options can be used in the scenarios shown in [TABLE 2-3](#)

TABLE 2-3 Installation Scenarios Using the `batch_installer` Command and Options

Scenario	Command Typed at the Prompt
Install in the default directory and generate a 60-day trial serial number by default	<code>#./batch_installer</code>
Install in the default directory with the permanent serial number	<code>#./batch_installer -s serial number</code>
Install in a directory other than the default directory	<code>#./batch_installer -d /dirname</code>
Install and change the root installation	<code>#./batch_installer -R /a/opt</code>

4. Choose the appropriate installation scenario from [TABLE 2-3](#) to run the `batch_installer` command. For example, to use the options to generate the 60-day Trial serial number and install in a directory other than the default, type the following:

```
# /cdrom/studio_8_sol_sparc/batch_installer -d /dirname
```

The Binary Code License Agreement appears, and the installer checks for adequate disk space. The installer proceeds with installation, and the prompt returns when installation is complete.

(Optional for electronic download) If you downloaded the product files from the product web site, type the following:

```
# /download-directory/install-directory/batch_installer -d /dirname
```

5. (Optional) If you performed the installation using a remote display, on the display computer, disable client access by typing the following:

```
% xhost - source-machine-name
```

6. Exit from superuser privileges on the source computer by typing:

```
# exit
```

7. Set your `PATH` and `MANPATH` variables. See [“Setting Up Access to the Developer Tools and Man Pages” on page 38](#).

Using the Solaris JumpStart Installer

You can use the Solaris JumpStart™ installer on the Solaris™ 9 operating system (SPARC® Platform Edition) and on the Solaris™ 9 operating system (x86 Platform Edition) to automate the software installation process to install the Sun Studio 8 software on multiple systems. An overview of the JumpStart installation steps is listed below. See the *Solaris 9 Installation Guide* for complete details of JumpStart installation.

Note – In the following instructions, substitute the download directory name for the `cdrom_path` that is used in the command-line examples.

1. Verify that you have more than one gigabyte of disk space in both the `swap` partition and the `/opt` partition on the source machine.
2. Copy the downloaded file into the `$SI_CONFIG_DIR` directory.

3. Create a finish script that resides on the source machine. The file must contain the following information:

```
#!/bin/sh
cd $SI_CONFIG_DIR/cdrom_path
./batch_installer -R /a
```

Note – The `batch_installer -d` option does not work in JumpStart installation.

See “Using the Batch Installer” on page 34 for information on the available `batch_installer` command options.

Refer to the *Solaris 9 Installation Guide* for further instruction on completing the JumpStart installation process.

Installing the J2SE Platform and Related Solaris Operating System Patches

The Sun Studio 8 Integrated Development Environment (IDE) supports the Java™ 2 Platform, Standard Edition technology (the J2SE™ technology) and related Solaris™ Operating System (OS) patches.

If you have the supported J2SE technology installed on your system, then the J2SE selection is not visible in the Select Components page of the installer.

If you do not have the supported J2SE technology installed on your system, then you can install the technology on your system by using one of these installers:

- The `studio_8_sol_sparc_companion` CD-ROM for the Solaris OS SPARC® platform. Using the companion CD-ROM, follow the instructions in “Using the Graphical User Interface Installer” on page 28 to install the J2SE technology.
- The `studio_8_sol_x86` CD-ROM for the Solaris OS x86 platform. During product installation, if you selected a default installation, then the J2SE technology is installed on your system. If you did not install the J2SE technology during the product installation, then run the installer again and select J2SE SDK 1.4.2 Solaris OS Patches in the Select Components page.
- A downloadable file available on the download page of the product web site at <http://www.sun.com/software/sundev/suncc/index.html>
The file names are:
 - `studio8-sol-sparc-j2sdk.tar` for the Solaris SPARC platform

- `studio8-sol-x86-j2sdk.tar` for the Solaris x86 platform

See the Download Instructions available on the product web site download page for more information on extracting the tar file. Follow the instructions in [“Using the Graphical User Interface Installer” on page 28](#) to install the J2SE technology.

Verifying a Successful Installation

Once the installation is completed, you can use any of the following methods to verify a successful installation:

- View the information in the Installation Summary page of the installer, which lists all products that are installed.
- Use the Solaris Product Registry to view all installed products. Type `prodreg` to open the Product Registry.
- View the installation log files.

a. Go to the `logs` directory by typing at the prompt:

```
% cd /var/sadm/install/logs
```

b. View the file by typing:

```
% more Sun_Studio_Software_install.A03200125
```

The file extension varies for each log file.

Setting Up Access to the Developer Tools and Man Pages

Because the Sun Studio 8 software product components and man pages are not installed into the system directories `/usr/bin/` and `/usr/share/man`, you must change your `PATH` and `MANPATH` environment variables to enable use of the Sun Studio 8 software.

Note – The paths shown in this section assume that Sun Studio 8 packages are installed in the default `/opt` directory. If you installed the software in a different directory, replace `/opt` in the examples with that directory name.

Set the `PATH` and `MANPATH` variables in your home environment files. In the examples that follow, the `.cshrc` file is shown if you are using the C shell, and the `.profile` file is shown if you are using the Bourne shell or Korn shell.

For more information about the `PATH` and `MANPATH` environment variables, the SunOS™ man page `csh(1)` describes the `PATH` variable for the C shell, the `sh(1)` man page describes the `PATH` variable for the Bourne shell, and the `ksh(1)` man page describes the `PATH` variable for the Korn shell. The `man(1)` man page describes the `MANPATH` variable.

Setting Your `PATH` Environment Variable So You Can Access Sun Studio 8 Tools

To use the Sun Studio 8 software commands, your `PATH` environment variable must contain the path `/opt/SUNWspro/bin`. To determine whether you need to set your `PATH` environment variable, follow these steps:

1. Display the current value of the `PATH` variable by typing:

```
% echo $PATH
```

2. Review the output for a string of paths that contain `/opt/SUNWspro`.

- If you find the path, your `PATH` variable is already set to access Sun Studio 8 software tools. (The `/opt` path can be replaced by an alternative install path.)
- If you do not find the path, set your `PATH` variable as described in [Step 3](#).

3. Add the path `/opt/SUNWspro/bin` to your `PATH` environment variable. If you have previous versions of Sun ONE Studio or Forte Developer software installed, add the path before the paths of the previous installations.

Note – Substitute your home environment file name for the file names shown in the examples.

- If you are using the C shell, edit your home `.cshrc` file to add the path.
- If you are using the Bourne shell or Korn shell, edit your home `.profile` file to add the path.

Setting Your MANPATH Environment Variable So You Can Access Sun Studio 8 Man Pages

To access Sun Studio 8 software man pages with the `man` command, your `MANPATH` environment variable must contain the path `/opt/SUNWspro/man`. To determine whether you need to set your `MANPATH` environment variable, follow these steps:

1. Request the `dbx(1)` man page by typing:

```
% man dbx
```

2. Review the output, if any.

If the `man dbx` command cannot find the `dbx(1)` man page, or if the page that is displayed is not for the version of the software you just installed, you do not have the `MANPATH` variable set correctly. Set your `PATH` variable as described in the next step.

3. Add the path `/opt/SUNWspro/man/` to your `MANPATH` environment variable.

- If you are using the C shell, edit your home `.cshrc` file to add the path.
- If you are using the Bourne shell or Korn shell, edit your home `.profile` file to add the path.

Adding the Changes to the Appropriate Environment Variable

The following procedure lets you permanently add the paths for the Sun Studio 8 software tools and man pages to the appropriate environment variables so that all Sun Studio 8 components are always available. These commands can also be entered at a shell prompt to temporarily enable that shell only.

1. Add the Sun Studio 8 software to your `PATH` and `MANPATH` variables.

Note – The `PATH` and `MANPATH` variables must be set to include Sun Studio 8 software in each user's environment, which allows each user to use the installed software.

- If you are using the C shell (`csh`), first determine if your `MANPATH` variable is already set. At a shell prompt, type the command:

```
% echo $MANPATH
```

If the response is “Undefined variable” (C shell) or an empty line (Bourne shell or Korn shell), the `MANPATH` variable is not set. If paths to one or more man directories are displayed, the variable is set.

Now edit the `.cshrc` file in your home directory and add the following line at the end of the file:

```
set path=(/opt/SUNWspro/bin $path)
```

If the `MANPATH` variable is not already set, add the following line:

```
setenv MANPATH /opt/SUNWspro/man:/usr/share/man
```

If the `MANPATH` variable is already set, add the following line instead:

```
setenv MANPATH /opt/SUNWspro/man:$MANPATH
```

- If you are using the Bourne or Korn shells (`sh` or `ksh`), edit the `.profile` file in your home directory and add the following lines:

```
PATH=/opt/SUNWspro/bin${PATH:+:}${PATH}
MANPATH=/opt/SUNWspro/man:${MANPATH:=/usr/share/man}
```

Do not type any spaces in these two lines.

2. Save the `.cshrc` file or `.profile` file that you modified in [Step 1](#).
3. Reinitialize your shell by executing the following command:

For the C shell, type:

```
source ~/.cshrc
```

For the Bourne shell or Korn shell, type:

```
. ~/.profile
```


Starting and Setting Up the Sun Studio 8 IDE

This chapter describes how to run and setup the Sun™ Studio 8 software on your system.

Starting the IDE

Once you have the Sun Studio 8 software installed on your system, and you have the Java™ 2, Standard Edition (J2SE™) technology on your system or the path to where it is installed on the network, you can start using the software. To start the product, do the following:

- **At the prompt, type:**

```
% sunstudio
```

Note – The full path to the command is
/installation-directory/SUNWspro/bin/sunstudio.

The Welcome page opens, and the Setup Wizard opens automatically the first time you run the Sun Studio 8 software. See [“Using the Setup Wizard” on page 44](#) for information on setting the parameters to use the software.

If the software cannot find the supported J2SE technology, you will receive an error message. The `sunstudio` command looks for the J2SE technology in your `PATH` and in several standard locations on your system. If the J2SE technology is not installed on your system, do one of the following:

- Use the `-jdkhome` option with the `sunstudio` command to specify the path to the J2SE technology on the network.

- Set the `JDK_HOME` environment variable to the path to the J2SE technology on the network. Reinitialize your shell, then type the `sunstudio` command again.

For more information on the options available with the `sunstudio` command, see the `sunstudio (1)` man page. For more information about using the IDE, see the *Integrated Development Environment (IDE) Readme*.

Using the Setup Wizard

The Setup wizard opens the first time you run the IDE. You can open the Setup wizard from the IDE Welcome screen click the Setup Wizard button. You can also open the Setup wizard by selecting Tools→Setup Wizard. In the Setup wizard, you can indicate your preferred settings for general Sun Studio 8 settings and for your text editor.

In the General Sun Studio Settings page, you can set the Window Mode, Web Browser, and Web Proxy. Choose your preferred display under Window Mode. For Web Browser, the External Browser (UNIX®) selection is the recommended choice. If you want to view any external web pages through the IDE, then you also have to indicate a Web Proxy.

In the Text Editor Preferences page, you can select your text editor of choice. The default selection is the Built-in Editor.

The Module Installation and Update Center pages of the Setup Wizard are not integral to the Sun Studio 8 IDE. Once you have selected your General Sun Studio Settings and the Text Editor Preferences, you can exit the Setup Wizard by clicking the Finish button. Your settings are saved.

The Welcome screen of the IDE includes a list of links that you can use to help you get started using the IDE, including a Getting Started section and a tutorial. For further information on viewing the compiler documentation, see [“Accessing Compilers and Tools Documentation” on page 11](#).

Using the Registration Wizard

The Registration wizard opens the first time you run the IDE. You can also open the Registration wizard by clicking Help→Registration Wizard. You can choose to register online, by fax, or by mail.

Note To System Administrators

After you have installed the Sun Studio 8 software, you can send an email to the developers who will be using the software. An email template is available in the following directory:

/installation-directory/SUNWspro/READMEs/email_template.txt

The email template provides information for:

- Setting local environment variables
- Starting the IDE
- Locating product documentation
- Installing the J2SE technology locally

The J2SE technology should be in the environment path of each developer who is using the Sun Studio 8 software. The developers can have the J2SE technology installed locally or mapped in their path environment. To assist the developers in installing the J2SE environment, you can copy the `studio8-sol-platform-j2sdk.tar` file or mount the CD-ROM image on a network server that is available to the developers. Be sure to include the path to J2SE installer in the email that you send to the developers.

Uninstalling Sun Studio 8 Software

This chapter describes how to uninstall the Sun™ Studio 8 software products and associated patches that are installed on your system.

When you successfully install your software, an uninstaller is automatically generated. There are four ways to use the uninstaller to remove the Sun Studio 8 software:

- Use the batch uninstaller, which removes all Sun Studio 8 software in silent mode. See [“Using the Batch Software Uninstaller” on page 49](#).
- Use the graphical user interface (GUI) uninstaller, which allows you to uninstall select Sun Studio 8 product components. See [“Using a Graphical User Interface Uninstaller” on page 50](#).
- Use the command-line uninstaller, which allows you to uninstall select Sun Studio 8 product components in silent or interactive mode. See [“Using a Command-Line Uninstaller” on page 52](#).
- Use the Solaris Product Registry tool, which allows you to uninstall select Sun Studio 8 product components. See [“Using the Solaris Product Registry Software Uninstaller” on page 53](#).

Note – Do not use the `pkgrm` command to uninstall the software. Use the provided uninstaller.

Note – If you are using Solaris OS 7, you need to run the uninstaller using the `-j` option with the following syntax: `./uninstaller -j /usr/java1.2` so the uninstaller can find the required J2SE 1.2 software.

Uninstalling When Previous Versions Of Sun ONE Studio Are Installed

If you installed the Sun Studio 8 software on a system that also has Sun Open Net Environment (ONE) Studio 8 software installed, then both versions are removed when you run the uninstaller. If you installed the Sun Studio 8 software on a system that has previous compiler collection installations other than Sun ONE Studio 8, then only the Sun Studio 8 software is removed when you use the uninstaller.

Choosing Local Display or Remote Display of an Uninstaller

You can display an uninstaller either locally or remotely while you are uninstalling Sun Studio 8 software.

To uninstall using the local display, proceed to [“Using a Graphical User Interface Uninstaller” on page 50](#) or [“Using a Command-Line Uninstaller” on page 52](#). To uninstall using a remote display, follow the steps in [“Preparing to Uninstall Using a Remote Display” on page 48](#), and then proceed to [“Using a Graphical User Interface Uninstaller” on page 50](#) or [“Using a Command-Line Uninstaller” on page 52](#).

Preparing to Uninstall Using a Remote Display

To prepare for uninstallation using a remote display, follow these steps:

1. **On the display computer, enable client access to the X server by typing the following at a command line:**

```
% xhost + source-computer-name
```

Replace *source-computer-name* with the output of the `/usr/bin/hostname` command entered on the source computer, which is the computer on which the uninstaller will be running.

2. **Log in to the source computer and become a superuser (root) by typing:**

```
% rlogin source-computer-name -l rootname  
Password: root-password
```

3. On the source computer, set your display to the monitor that is attached to the display computer.

If you use the C shell, type:

```
# setenv DISPLAY display-computer-name:0.0
```

If you use the Bourne shell, type:

```
# DISPLAY=display-computer-name:0.0  
# export DISPLAY
```

If you use the Korn shell, type:

```
# export DISPLAY=display-computer-name:0.0
```

Replace *display-computer-name* with the output of the `/usr/bin/hostname` command on the display computer, which is the computer on which the uninstaller will be displayed.

Using the Batch Software Uninstaller

The batch uninstaller removes all Sun Studio 8 software in the silent mode.

1. Become a superuser (root) by typing:

```
% su  
Password: root-password
```

2. Go to the product directory by typing:

```
# cd /var/sadm/prod/com.sun.studio_8
```

Note – If you are uninstalling an Early Access version of the product, the uninstaller directory is `/var/sadm/prod/com.sun.sls8_solaris_edition_ea1`.

3. Start the batch uninstaller by typing:

```
# ./uninstaller
```

The batch uninstaller starts and continues with uninstallation.

Using a Graphical User Interface Uninstaller

TABLE 4-1 shows the software names and the `uninstaller.class` file names that you use to uninstall the Sun Studio 8 software.

TABLE 4-1 Software Names and Related Uninstaller `.class` File Names

Software Name	Uninstallation <code>.class</code> File Names
Sun Performance Library 8	<code>uninstall_Sun_Performance_Library.class</code>
Source Distribution	<code>uninstall_Source_Distribution.class</code>
IDE and tools software	<code>uninstall_Sun_Studio_Software.class</code>
Documentation	<code>uninstall_Documentation.class</code>
Uninstaller class files are located at <code>/var/sadm/prod/com.sun.studio_8</code>	

To run an uninstaller, follow these steps:

1. If you have not already done so, become a superuser (root) by typing:

```
% su
Password: root-password
```

2. Go to the uninstaller directory by typing:

```
# cd /var/sadm/prod/com.sun.studio_8
```

3. Determine the uninstaller `.class` file name for the software you want to uninstall by typing `ls -l` to see the list of uninstaller `.class` file names or referring to TABLE 4-1.

4. To start the uninstaller, type the following, using the appropriate uninstaller .class file name.

Note – Do not include the .class extension of the file name when you type the command.

```
# /usr/bin/java uninstall_uninstaller-class-file-name
```

For example, to remove the Sun Studio 8 software, type:

```
# /usr/bin/java uninstall_Sun_Studio_Software
```

The Uninstalling window appears. The Welcome page shows you which products will be uninstalled.

5. In the Welcome page, click **Next to continue**.

The Select Type of Uninstall page appears.

6. In the Select Type of Uninstall page, select the type of uninstallation you want:

If you want to uninstall all of the components of the product, select Full. Click Next and proceed to [Step 8](#).

If you want to uninstall only certain components of the product, select Partial. Click Next and proceed to [Step 7](#).

7. In the Component Selection page, deselect the components you do not want to uninstall by clicking their checkboxes to remove the check marks. Click Next to continue.

8. In the Ready to Uninstall page, click **Uninstall Now**.

The Uninstalling page appears with a progress indicator. When uninstallation is complete, the Uninstallation Summary page appears. Click the Details button to view the log files.

9. Click **Exit** to exit the uninstaller.

10. (Optional) If you performed the uninstallation using a remote display, on the display computer, disable client access by typing the following:

```
% xhost - source-computer-name
```

11. Exit from superuser privileges on the source computer by typing:

```
# exit
```

Using a Command-Line Uninstaller

To remove software products with the command-line uninstaller, follow these steps:

1. Become a superuser (root) by typing:

```
% su
Password: root-password
```

2. Go to the product directory by typing:

```
# cd /var/sadm/prod/com.sun.studio_8
```

3. To determine the uninstaller `.class` file name for the software you want to uninstall, type `ls -l` to see the list of uninstaller `.class` file names or refer to [TABLE 4-1](#).
4. Type one of the following commands to run the command-line uninstaller, using the appropriate uninstaller `.class` file name.

Note – Do not include the `.class` extension of the file name when you type the command.

- To uninstall a product using its interactive command-line uninstaller, type:

```
# /usr/bin/java uninstall_uninstaller-class-file-name -nodisplay
```

For example, to uninstall the Sun Studio 8 software, type:

```
# /usr/bin/java uninstall_Sun_Studio_Software -nodisplay
```

The installer shows you which product will be uninstalled. Proceed to [Step 5](#).

- To uninstall the entire product without any additional prompts (in silent mode), type:

```
# /usr/bin/java uninstall_uninstaller-class-file-name -nodisplay -noconsole
```

The product is uninstalled and the uninstaller exits. Proceed to [Step 7](#).

5. Press Enter to continue.
6. Follow the command-line instructions to complete the uninstallation.
7. When uninstallation is complete, you have the option to view the product's log file by typing its corresponding number. When finished, type the number that corresponds to Done.

The installer exits.

8. (Optional) If you performed the uninstallation using a remote display, on the display computer, disable client access by typing the following:

```
% xhost - source-computer-name
```

9. Exit from superuser privileges on the source computer by typing:

```
# exit
```

Using the Solaris Product Registry Software Uninstaller

You can use the Solaris Product Registry tool to start the uninstaller.

1. Become a superuser (root) by typing:

```
% su  
Password: root-password
```

2. At the prompt, type:

```
# prodreg
```

3. From the Registered Software column, select the software component you want to uninstall.
4. Click the Uninstall button, and the uninstaller opens.
5. Verify that you want to uninstall that component and click OK in the Warning dialog.
6. (Optional) You might be prompted to use the interactive uninstaller. Follow the instructions in the uninstaller wizard to complete the uninstallation.

Troubleshooting

This chapter describes how to fix problems that can occur during Sun™ Studio 8 software installation and uninstallation.

Installing in a Directory That Is Reached by a Symbolic Link

You can install in a directory where part of the path is a symbolic link. An example for installing in a path reached by a symbolic link is if the default directory `/opt` does not have enough disk space. You need to complete the steps below to prevent the installer from bypassing the symbolic link and installing in an actual filesystem.

Note – For example, if you choose to install in `/opt`, the following steps show you how to create a symbolic link of `/opt/SUNWspro` that points to `/export/opt_SUNWspro`. You can substitute your directory names for the example names.

1. Become a superuser (root) by typing:

```
% su
Password: root-password
```

2. Save the existing symbolic link by typing:

```
# mv /opt/SUNWspro /mytemp
```

3. Make a new `/opt/SUNWspro` directory, which will serve as a mount point, by typing:

```
# mkdir /opt/SUNWspro
```

4. Mount the target directory so it is available as `/opt/SUNWspro` by typing:

```
# mount -F nfs localhost:/export/opt_SUNWspro /opt/SUNWspro
```

5. Install the product in the `/opt` directory.

6. Unmount the target directory by typing:

```
# umount /opt/SUNWspro
```

7. Remove the empty `/opt/SUNWspro` mount point by typing:

```
# rmdir /opt/SUNWspro
```

8. Restore the symbolic link that you moved in [Step 2](#):

```
# mv /mytemp /opt/SUNWspro
```

9. Exit from superuser privileges by typing:

```
# exit
```

Product Registry Problems

If you encounter installation or uninstallation problems that involve a corrupt `productregistry` file, you can sometimes use the Solaris™ Product Registry Tool to locate and fix the problem.

How Do I Identify and Fix a Failed Installation?

If some packages are not properly installed, you will have problems using the Sun[™] Studio software. For example, if you used the `pkgadd` command to install the software, you have corrupted the `productregistry` file. To verify whether all packages are installed properly, follow these instructions:

1. **Become a superuser (root) by typing:**

```
% su
Password: root-password
```

2. **Open the Solaris Product Registry tool by typing:**

```
% /usr/bin/prodreg &
```

3. **In the left column of the tool, look at the list under the heading Registered Software.**

If a yellow triangle appears adjacent to the product name, then the product is not installed properly.

4. **Select the product name and click the Uninstall button.**

The Uninstall Failed dialog box opens.

5. **Read the message in the box, and then click OK if you want to uninstall the product.**

The Interactive Uninstall dialog box opens.

6. **Follow the instructions in the subsequent dialog boxes until uninstallation is complete.**

Once the uninstallation is complete, you can reinstall the product software using the product installer. See [Chapter 2](#) for product installation instructions.

How Do I Fix a Failed Uninstallation?

If the uninstaller quits before all the product files are deleted, rerunning the uninstaller will not delete the remaining product files. The product files have been marked as deleted in the `productregistry` file, so the uninstaller does not remove the remaining files. To completely remove the product files, use the Solaris Product Registry tool, as described in the following procedure:

1. Become a superuser (root) by typing:

```
% su
Password: root-password
```

2. Open the Solaris Product Registry tool by typing:

```
# /usr/bin/prodreg &
```

3. In the left column of the tool, select all product names containing S1S8 or Sun Studio 8 and click the Uninstall button.

The Uninstall Failed dialog box opens.

4. Read the message in the box, and then click OK if you want to uninstall the product.

The Interactive Uninstall dialog box opens.

5. Follow the instructions in the subsequent dialog boxes until uninstallation is complete.

Once the uninstallation is complete, you can reinstall the product software using the product installer. See [Chapter 2](#) for product installation instructions.

What Can I Do If the productregistry File Is Corrupted?

If you attempted to fix the failed installation or uninstallation by using the steps in [“How Do I Identify and Fix a Failed Installation?” on page 57](#) or [“How Do I Fix a Failed Uninstallation?” on page 57](#), and you are still having problems, you need to delete the corrupted productregistry file from your system. The productregistry file is typically corrupted if you attempt to install or uninstall the software using the pkgadd command or pkgrm command.

Note – Deleting the productregistry file removes the entries for the Sun Studio 8 software and the registry entries for the Solaris Operating System (OS) and other products. Review the steps in [“How Do I Identify and Fix a Failed Installation?” on page 57](#) and [“How Do I Fix a Failed Uninstallation?” on page 57](#) before proceeding with the steps below.

1. Become a superuser (root) by typing:

```
% su
Password: root-password
```

2. Go to the `productregistry` file by typing the following command at the prompt:

```
% cd /var/sadm/install
```

3. Remove the `productregistry` file by typing:

```
# rm productregistry
```

4. Exit from superuser privileges by typing:

```
# exit
```

Once you have removed the `productregistry` file, you can reinstall the product software using the product installer. See Chapter 2 for product installation instructions.

Log Files and Serial Number Files

When you install the Sun Studio software, log files that contain a record of the installation are automatically generated.

How Can I View the Installation Log Files?

To troubleshoot installation problems by viewing the log files, do the following:

1. Go to the `logs` directory by typing at the prompt:

```
% cd /var/sadm/install/logs
```

2. View the file by typing:

```
% more Sun_Studio_Software_install.A03200125
```

The file extension varies for each log file.

How Do I Find the Installed Serial Number?

You need the serial number to register the product. You can find the serial number by using the `snit` tool.

To find and view the contents of the `serial.dat` file, type the following:

```
% /install-directory/SUNWspro/bin/snit -d -f /install-  
directory/SUNWspro/prod/lib/serial.dat
```

For more information, see the `snit(1)` man page. If `snit` is not recognized as a command, set your `PATH` environment variable, as described in [“Setting Up Access to the Developer Tools and Man Pages” on page 38](#).

What Can I Do If I Lose My Serial Number?

If you lose your serial number and cannot view the contents of the `serial.dat` file or display your serial number with the `snit` command, contact customer support at <http://www.sun.com/software/sundev/suncc/support.html>

Installing With a Remote Display Installation

The following topics include problems that can occur during a remote display installation.

What If the Installation Fails on an NFS-Mounted Filesystem?

If the installation fails on an NFS-mounted filesystem, ensure that you have write permission on that filesystem. You can check for write permission by following the instructions below. See [“Choosing Local Display or Remote Display of the Installer” on page 19](#) for more information about installing on an NFS-mounted filesystem.

1. Check for write permission by typing:

```
% touch /net/remote-system/opt/testfile
```

If you receive an error message, then you do not have write permission. For example:

```
% touch /net/harker/opt/testfile
touch: /net/harker/opt/testfile cannot create
```

2. Choose another installation directory on which you have write permission, or contact your system administrator to change the filesystem permissions.

How Do I Initialize a ToolTalk Software Session During Remote Display Installation?

If the graphical user interface installer stalls during installation, you can initialize a ToolTalk™ software session by doing the following:

1. Exit from the installer.
2. If you are not currently superuser (root), become a superuser by typing:

```
% su
Password: root-password
```

3. Type at the prompt:

```
# /usr/dt/bin/ttsession -c
```

4. Ensure that the \$DISPLAY is set.

The sections [“Preparing to Install Using a Remote Display” on page 19](#) and [“Preparing to Install Using a Remote Display With an NFS-Mounted Filesystem” on page 20](#) describe how to set the remote display.

5. Start the installer by typing:

```
# /cdrom/studio_8_sol_arch/installer
```

Follow the instructions in [Chapter 2](#) to complete the installation.

What Can I Do If the Batch Installer Stalls?

If you enter an invalid parameter when you start the batch installer, the installer stalls and does not complete the installation. Some common errors include typing an incorrect serial number, including two different directory names, or invoking the installer when you do not have enough disk space.

Follow these steps to restart the batch installer:

1. View the log files for any error messages by typing:

```
% cd /var/sadm/install/logs
```

2. To stop the installer, press Control+C.

3. To install the product using the batch installer, see [“Using the Batch Installer” on page 34 of Chapter 2](#).

Workaround for Sun Studio Installation on the Solaris 7 OS

If your server has Solaris 7 Operating System (OS) installed, you need to verify that the J2SE 1.2 technology is installed on that server before you can run the Sun Studio 8 installer. The J2SE installer included with the Sun Studio 8 product can install the proper J2SE technology and related Solaris OS patches on your system. In some cases, if your system requires a kernel patch, you have to reboot your system after the kernel patch is installed. If you do not want to reboot your server, you can install the Sun Studio 8 software in a network-mounted directory. You can avoid rebooting your server by installing the product using this command:

```
# - ./batch_installer -R /alternate_read_write_mountable_directory
```

If you want to add patches to the product, then use the `-R` option with the `patchadd` command. See the `patchadd` man page for more information. When you install using the `-R` option, the product registry is not updated by the installer. To uninstall a product that was installed using the `-R` option, remove the directory from the system.

Sun Studio 8 Components and Packages

This appendix provides information about the Sun Studio 8 software products available for software development. This appendix also lists the components and packages that comprise each product.

[TABLE A-1](#) lists the Sun Studio 8 software metacluster and package configuration and component information for the Solaris™ Operating System (*SPARC® Platform Edition*). Component names are in all uppercase characters. For example, the `SPROLANG` component is listed in the Package and Component Lists for the `SPROCC` component and the `SPROCCC` component, indicating that all of the packages in the `SPROLANG` component are included in the `SPROCC` component and the `SPROCCC` component.

[TABLE A-2](#) lists the Sun Studio 8 software metacluster and package configuration and component information for the Solaris OS (*x86 Platform Edition*). Component names are in all uppercase characters. For example, the `SPROLANG` component is listed in the Package and Component Lists for the `SPROCC` component and the `SPROCCC` component, indicating that all of the packages in the `SPROLANG` component are included in the `SPROCC` component and the `SPROCCC` component.

TABLE A-1 Sun Studio 8 Product Metacluster Components and Packages for Solaris
SPARC Platform Edition

Sun Studio Software (SPROMSTUDIO)
Sun Studio 8 Compilers C (SPROCC)
Sun Studio 8 Compilers Common Components (SPROLANG)
Sun Studio 8 Incremental Linker (SPROILD)
Sun Studio 8 Compiler C (SPROcc)
Sun Studio 8 Common Tools (SPROutool)
Sun Studio 8 Man Pages/Online Info for C (SPROmrcc)
Sun Studio 8 Common Compiler Man Pages/Online Info (SPROmrcom)
Sun Studio 8 Incremental Linker Man Page (SPROmrild)
Sun Studio 8 Math Library Man Pages (SPROmr3m)
Sun Studio 8 Test Coverage Man Page (SPROmrtdcv)
Sun Studio 8 dmake Man Page (SPROmrtdmk)
DwarfSupportLibrary man pages (SPROmrtdwf)
Sun Studio 8 IDE README (SPROmrtd)
Sun Studio 8 C9X Math Library (SPROM9XS)
Sun Studio 8 Sunmath Library (SPROSM)
Sun Studio 8 Man Pages/Online Info for Source Browser (SPROmrsbe)
Sun Studio 8 Source Browser (SPROsbe)
Serial Number Installation Tool and Misc files (SPROCMISC)

TABLE A-1 Sun Studio 8 Product Metacluster Components and Packages for Solaris
SPARC Platform Edition (Continued)

Sun Studio 8 Compilers C++ (SPROCCC)
Sun Studio 8 Compilers Common Components (SPROLANG)
Sun Studio 8 Incremental Linker (SPROILD)
Sun Studio 8 Compilers C++ (SPROCPL)
Sun Studio 8 Common Tools (SPROutool)
Sun Studio 8 C++ Complex Library (SPROcmpl)
Sun Studio 8 Tools.h++ 7.1 (SPROTL7)
Sun Studio 8 Standard Library for C++ (SPROSCL)
Sun Studio 8 Man Pages/Online Info for C++ (SPROmrctl)
Sun Studio 8 Common Compiler Man Pages/Online Info (SPROmrcom)
Sun Studio 8 Incremental Linker Man Page (SPROmrild)
Sun Studio 8 Math Library Man Pages (SPROmr3m)
Sun Studio 8 Test Coverage Man Page (SPROmrctv)
Sun Studio 8 dmake Man Page (SPROmrchk)
DwarfSupportLibrary man pages (SPROmrchk)
Sun Studio 8 IDE README (SPROmrchk)
Sun Studio 8 C9X Math Library (SPROM9XS)
Sun Studio 8 Man Pages/Online Info for Source Browser (SPROmrchk)
Sun Studio 8 Source Browser (SPROsbe)
Sun Studio 8 Sunmath Library (SPROSM)
Sun Studio 8 STLport (SPROSTLPORT)
Serial Number Installation Tool and Misc files (SPROCMISC)

TABLE A-1 Sun Studio 8 Product Metacluster Components and Packages for Solaris
SPARC Platform Edition (Continued)

Sun Studio 8 Compilers Fortran 95 (SPROCFOR)
Sun Studio 8 Compiler FORTRAN 77 Tools (SPROftool)
Sun Studio 8 Compilers Common Components (SPROLANG)
Sun Studio 8 Fortran 95 Libraries (SPROLIB90)
Sun Studio 8 Compiler Fortran 90 (SPROf90)
Sun Studio 8 Incremental Linker (SPROILD)
Sun Studio 8 Common Tools (SPROutool)
Sun Studio 8 Man Pages/Online Info for Fortran 95 (SPROmrftn)
Sun Studio 8 Common Compiler Man Pages/Online Info (SPROmrcom)
Sun Studio 8 Incremental Linker Man Page (SPROmrild)
Sun Studio 8 Math Library Man Pages (SPROmr3m)
Sun Studio 8 Test Coverage Man Page (SPROmrctv)
Sun Studio 8 dmake Man Page (SPROmrchk)
DwarfSupportLibrary man pages (SPROmrdfw)
Sun Studio 8 IDE README (SPROmrde)
Sun Studio 8 C9X Math Library (SPROM9XS)
Sun Studio 8 Sunmath Library (SPROSM)
Sun Studio 8 Man Pages/Online Info for Source Browser (SPROmrsbe)
Sun Studio 8 Source Browser (SPROsbe)
Serial Number Installation Tool and Misc files (SPROCMISC)

TABLE A-1 Sun Studio 8 Product Metacluster Components and Packages for Solaris
SPARC Platform Edition (Continued)

Sun Studio 8 Compilers Fortran 95 Legacy Libraries (SPROCFORL)
Sun Studio 8 Compiler FORTRAN 77 Tools (SPROftool)
Sun Studio 8 Compilers Common Components (SPROLANG)
Sun Studio 8 FORTRAN 77 Dynamic Libraries (SPROI77s)
Sun Studio 8 FORTRAN 77 64-bit Dynamic Libraries (SPROI77sx)
Sun Studio 8 Fortran 95 Libraries (SPROLIB90)
Sun Studio 8 Compiler Fortran 90 (SPROf90)
Sun Studio 8 Incremental Linker (SPROILD)
Sun Studio 8 Common Tools (SPROutool)
Sun Studio 8 Man Pages/Online Info for Fortran 95 (SPROMrftn)
Sun Studio 8 Common Compiler Man Pages/Online Info (SPROMrcom)
Sun Studio 8 Incremental Linker Man Page (SPROMrild)
Sun Studio 8 Math Library Man Pages (SPROMr3m)
Sun Studio 8 Test Coverage Man Page (SPROMrtcv)
Sun Studio 8 dmake Man Page (SPROMrdmk)
DwarfSupportLibrary man pages (SPROMrdwf)
Sun Studio 8 IDE README (SPROMride)
Sun Studio 8 C9X Math Library (SPROM9XS)
Sun Studio 8 Sunmath Library (SPROSM)
Sun Studio 8 Man Pages/Online Info for Source Browser (SPROMrsbe)
Sun Studio 8 Source Browser (SPROsbe)
Serial Number Installation Tool and Misc files (SPROCMISC)
Sun Studio 8 Garbage Collector (SPROCLGC)
Sun Studio 8 Garbage Collector (SPROLGC)
Sun Studio 8 Garbage Collector 64-bit Library (SPROLGCX)
Sun Studio 8 LockLint (SPROCLKLT)
Sun Studio 8 LockLint (SPROlklnt)
Sun Studio 8 Man Pages/Online Info for MT Tools (SPROMrmp)
Sun Studio 8 DBX Debugging Tools (SPROCDBX)
Sun Studio 8 Debugging Tools (SPROdbx)
Sun Studio 8 Debugging Tools 64-bit (SPROdbxx)
Sun Studio 8 Debugging Tools (SPROjdbx)
Sun Studio 8 Debugging Tools 64-bit (SPROjdbxx)
Sun Studio 8 Man Pages/Online Info for dbx (SPROMrdbx)
Serial Number Installation Tool and Misc files (SPROCMISC)

TABLE A-1 Sun Studio 8 Product Metacluster Components and Packages for Solaris
SPARC Platform Edition (Continued)

Sun Studio 8 Performance Tools (SPROCPRFT)
Sun Studio 8 Performance Analyzer Tools (SPROprfan)
Sun Studio 8 Man Pages/Online Info for Perf Tools (SPROmrpan)
Sun Studio 8 Performance Analyzer 64-bit Tools (SPROprfax)
Serial Number Installation Tool and Misc files (SPROCMISC)
Sun Studio 8 Demos (SPROCDemo)
Sun Studio 8 Compiler Examples and Programs (SPROdemo)
Sun Studio 8 Building Software (SPROCBLD)
Sun Studio 8 Distributed Make (SPROdmake)
Sun Studio 8 dmake Man Page (SPROmrchk)
Sun Studio 8 Demos (SPROCTDemo)
Sun Studio 8 Tools Examples and Programs (SPROtdemo)
Sun Studio 8 IDE (SPROCIDE)
Sun Studio 8 dbx GUI plug-in (SPROdbxui)
Sun Studio 8 X-designer plug-in (SPROxdplg)
Sun Studio 8 Performance Analyzer GUI (SPROprfgn)
Sun Studio 8 Man Pages/Online Info for Analyzer GUI (SPROmrpgn)
Sun Studio 8 Branding files (SPROidext)
Sun Studio 8 Native Connector Tool (SPROjnsnb)
Sun Studio 8 Native Connector Tool Run-Time (SPROjnsrt)
Sun Studio 8 Native Connector Tool Support (SPROjnsup)
Sun Studio 8 Licensing Management Tool (SPRONblic)
Sun Studio 8 Registration Tool (SPRONbreg)
Sun Studio 8 NetBeans (SUNWnbide)
Sun Studio 8 GUI interface support (SPROsvc)
Sun Studio 8 X-Designer (SPROCXD)
X-Designer GUI Builder (SPROfdxd)
X-Designer ManPages and Online Help (SPROmrxd)
External Editors (SPROCED)
Sun Studio 8 vim external editor (SPROgvim)
Sun Studio 8 XEmacs 21.4.12 (SPROxmbin)
Sun Studio 8 XEmacs 21.4.12 (SPROxmshr)
Sun Studio 8 XEmacs 21.4.12 - documentation (SPROmrxm)

TABLE A-1 Sun Studio 8 Product Metacluster Components and Packages for Solaris
SPARC Platform Edition (Continued)

Sun Studio 8 Documentation Set (SPROMDOCS)
Sun Studio 8 Documentation Set (SPROCDOCS)
Sun Studio 8 Copyright and Images (SPROhtbas)
Sun Studio 8 Release Docs (SPROhtrel)
Sun Studio 8 Tools.h++ 7.1 Docs (SPROhttl7)
Sun Studio 8 Standard Library C++ Docs (SPROhtstd)
Sun Studio 8 Compiler FORT 77/95 (SPROhtftn)
Sun Studio 8 C Compiler Docs (SPROhtcc)
Sun Studio 8 Common Tools Docs (SPROhtcom)
Sun Studio 8 C++ Compiler Docs (SPROhtcpl)
Sun Studio 8 OpenMP (SPROhtomp)
Sun Studio 8 Sun Performance Library Docs (SPROhtpl)
Sun Studio 8 Dbx Document (SPROhtdbx)
Sun Studio 8 Analyzer Document (SPROhtpan)
Sun Studio 8 X-Designer Document (SPROhtxd)
Sun Studio 8 Sun Performance Library (SPROMPLIB)
Sun Performance Library (SPROCPERF)
Sun Studio 8 Compilers Common Components (SPROLANG)
Sun Studio 8 Fortran 95 Libraries (SPROLIB90)
Sun Studio 8 Man Pages for Sun Perf Library (SPROmrpl)
Sun Studio 8 PerfLib Common Components (SPROplg)
Sun Studio 8 Unbundled Shared libsunmath (SPROsunms)
Sun Studio 8 libsunmath 64-bit (Shared) (SPROsmx)
Sun Studio 8 Performance Archive Libraries (SPROPL)
Sun Studio 8 Performance Shared Libraries (SPROPLS)
Sun Studio 8 Interval Libraries Common Components (SPROiplg)
Sun Studio 8 Man Pages for Sun Interval Library (SPROMripl)
Sun Studio 8 Interval Libraries 32-bit (SPROipl)
Sun Studio 8 Interval Libraries 64-bit (SPROiplx)
Sun Studio 8 Source Distribution (SPROMSRC)
DwarfLibrary, Source Distribution (DWSRC)
DwarfSupportLibrary source (SPROdwrfs)
Red-Black Tree Library, Source Distribution (RDBLKSRC)
Red-Black_Tree_Library source (SPROdbks)
XEmacs editor, Source Distribution (XMSRC)
Sun Studio 8 XEmacs 21.4.12 - source distribution (SPROxmsrc)
Sun Studio 8 STLport Source Distribution (STLSRC)
STLPort version 4 source (SPROstl4h)

TABLE A-2 Sun Studio 8 Product Metacluster Components and Packages for Solaris x86
Platform Edition

Sun Studio Software (SPROMSTUDIO)

Sun Studio 8 Compilers C (SPROCC)

Sun Studio 8 Compilers Common Components (SPROLANG)

Sun Studio 8 Incremental Linker (SPROILD)

Sun Studio 8 Compiler C (SPROcc)

Sun Studio 8 Common Tools (SPROutool)

Sun Studio 8 Man Pages/Online Info for C (SPROmrcc)

Sun Studio 8 Common Compiler Man Pages/Online Info (SPROmrcom)

Sun Studio 8 Incremental Linker Man Page (SPROmrild)

Sun Studio 8 Math Library Man Pages (SPROmr3m)

Sun Studio 8 Test Coverage Man Page (SPROmrctv)

Sun Studio 8 dmake Man Page (SPROmrchk)

DwarfSupportLibrary man pages (SPROmrdfw)

Sun Studio 8 IDE README (SPROmrde)

Sun Studio 8 C9X Math Library (SPROM9XS)

Sun Studio 8 Sunmath Library (SPROSM)

Sun Studio 8 Man Pages/Online Info for Source Browser (SPROmrbe)

Sun Studio 8 Source Browser (SPROsbe)

Serial Number Installation Tool and Misc files (SPROCMISC)

TABLE A-2 Sun Studio 8 Product Metacluster Components and Packages for Solaris x86 Platform Edition (Continued)

Sun Studio 8 Compilers C++ (SPROCCC)
Sun Studio 8 Compilers Common Components (SPROLANG)
Sun Studio 8 Incremental Linker (SPROILD)
Sun Studio 8 Compilers C++ (SPROCPL)
Sun Studio 8 Common Tools (SPROutool)
Sun Studio 8 C++ Complex Library (SPROcmpl)
Sun Studio 8 Tools.h++ 7.1 (SPROTL7)
Sun Studio 8 Standard Library for C++ (SPROSCL)
Sun Studio 8 Man Pages/Online Info for C++ (SPROmrcl)
Sun Studio 8 Common Compiler Man Pages/Online Info (SPROmrcom)
Sun Studio 8 Incremental Linker Man Page (SPROmrild)
Sun Studio 8 Math Library Man Pages (SPROmr3m)
Sun Studio 8 Test Coverage Man Page (SPROmrctv)
Sun Studio 8 dmake Man Page (SPROmrchk)
DwarfSupportLibrary man pages (SPROmrchk)
Sun Studio 8 IDE README (SPROmrchk)
Sun Studio 8 C9X Math Library (SPROM9XS)
Sun Studio 8 Man Pages/Online Info for Source Browser (SPROmrsbe)
Sun Studio 8 Source Browser (SPROsbe)
Sun Studio 8 Sunmath Library (SPROSM)
Sun Studio 8 STLport (SPROSTLPORT)
Serial Number Installation Tool and Misc files (SPROCMISC)
Sun Studio 8 Garbage Collector (SPROCLGC)
Sun Studio 8 Garbage Collector (SPROLGC)
Sun Studio 8 DBX Debugging Tools (SPROCDXB)
Sun Studio 8 Debugging Tools (SPROdbx)
Sun Studio 8 Debugging Tools (SPROjdbx)
Sun Studio 8 Man Pages/Online Info for dbx (SPROmrdbx)
Serial Number Installation Tool and Misc files (SPROCMISC)
Sun Studio 8 Performance Tools (SPROCPRFT)
Sun Studio 8 Performance Analyzer Tools (SPROprfan)
Sun Studio 8 Man Pages/Online Info for Perf Tools (SPROmrpan)
Serial Number Installation Tool and Misc files (SPROCMISC)
Sun Studio 8 Demos (SPROCDemo)
Sun Studio 8 Compiler Examples and Programs (SPROdemo)
Sun Studio 8 Building Software (SPROCBLD)
Sun Studio 8 Distributed Make (SPROdmake)
Sun Studio 8 dmake Man Page (SPROmrchk)

TABLE A-2 Sun Studio 8 Product Metacluster Components and Packages for Solaris x86 Platform Edition (Continued)

Sun Studio 8 Demos (SPROCTDEMO)
Sun Studio 8 Tools Examples and Programs (SPROtdemo)
Sun Studio 8 IDE (SPROCIDE)
Sun Studio 8 dbx GUI plug-in (SPROdbxui)
Sun Studio 8 X-designer plug-in (SPROxdplg)
Sun Studio 8 Performance Analyzer GUI (SPROprfgn)
Sun Studio 8 Man Pages/Online Info for Analyzer GUI (SPROmrpgn)
Sun Studio 8 Branding files (SPROidext)
Sun Studio 8 Native Connector Tool (SPROjnsnb)
Sun Studio 8 Native Connector Tool Run-Time (SPROjnsrt)
Sun Studio 8 Native Connector Tool Support (SPROjnsup)
Sun Studio 8 Licensing Management Tool (SPRONblic)
Sun Studio 8 Registration Tool (SPRONbreg)
Sun Studio 8 NetBeans (SUNWnbide)
Sun Studio 8 GUI interface support (SPROsvc)
Sun Studio 8 X-Designer (SPROCXD)
X-Designer GUI Builder (SPROfdxd)
X-Designer ManPages and Online Help (SPROmrxd)
External Editors (SPROCED)
Sun Studio 8 vim external editor (SPROgvim)
Sun Studio 8 XEmacs 21.4.12 (SPROxmbin)
Sun Studio 8 XEmacs 21.4.12 (SPROxmshr)
Sun Studio 8 XEmacs 21.4.12 - documentation (SPROmxm)
Sun Studio 8 Documentation Set (SPROMDOCS)
Sun Studio 8 Documentation Set (SPROCDPCS)
Sun Studio 8 Copyright and Images (SPROhtbas)
Sun Studio 8 Release Docs (SPROhtrel)
Sun Studio 8 Tools.h++ 7.1 Docs (SPROhttl7)
Sun Studio 8 Standard Library C++ Docs (SPROhtstd)
Sun Studio 8 Dbx Document (SPROhtdbx)
Sun Studio 8 Analyzer Document (SPROhtpan)
Sun Studio 8 C Compiler Docs (SPROhtcc)
Sun Studio 8 Common Tools Docs (SPROhtcom)
Sun Studio 8 C++ Compiler Docs (SPROhtcpl)
Sun Studio 8 X-Designer Document (SPROhtxd)

TABLE A-2 Sun Studio 8 Product Metacluster Components and Packages for Solaris *x86 Platform Edition (Continued)*

Sun Studio 8 Source Distribution (SPROMSRC)
DwarfLibrary, Source Distribution (DWSRC)
DwarfSupportLibrary source (SPROdwrfbs)
Red-Black Tree Library, Source Distribution (RDBLKSRC)
Red-Black_Tree_Library source (SPROdbks)
XEmacs editor, Source Distribution (XMSRC)
Sun Studio 8 XEmacs 21.4.12 - source distribution (SPROxmsrc)
Sun Studio 8 STLport Source Distribution (STLSRC)
STLPort version 4 source (SPROstl4h)

Patch Identification Numbers and Descriptions

Operating system patches and product patches are provided for Sun™ Studio 8 software. These patches are required for the proper operation of the compilers and tools in this release. This appendix lists both the Solaris™ Operating System (OS) patches and the Sun Studio 8 patches that are included with this release. These patches are installed automatically unless you change the default selection on the Select Components page during the installation process.

TABLE B-1 lists the patch identification numbers and descriptions for the Solaris 7 OS (*SPARC® Platform Edition*).

TABLE B-2 lists the patch identification numbers and descriptions for the Solaris 7 OS (*x86 Platform Edition*).

TABLE B-3 lists the patch identification numbers and descriptions for the Solaris 8 OS (*SPARC® Platform Edition*).

TABLE B-4 lists the patch identification numbers and descriptions for the Solaris 8 OS (*x86 Platform Edition*).

TABLE B-5 lists the patch identification numbers and descriptions for the Solaris 9 OS (*SPARC® Platform Edition*).

TABLE B-6 lists the patch identification numbers and descriptions for the Solaris 9 OS (*x86 Platform Edition*).

TABLE B-1 Patches Installed With Sun Studio 8 Software for Solaris 7 *SPARC Platform Edition*

Patch Identification Number	Patch Description
106950-24	Linker (32-bit)
106327-20 (requires 106950-13)	Solaris 7 C++ runtime support libraries (32-bit)

TABLE B-1 Patches Installed With Sun Studio 8 Software for Solaris 7 *SPARC Platform Edition (Continued)*

Patch Identification Number	Patch Description
106300-21 (requires 106327-20)	Solaris 7 C++ runtime support libraries (64-bit)
106748-04	SCCS and make (32-bit)
107058-02	Assembler (64-bit)

TABLE B-2 Patches Installed With Sun Studio 8 Software for Solaris 7 *x86 Platform Edition*

Patch Identification Number	Patch Description
106951-25	Linker (32-bit)
106328-18	Solaris 7 C++ runtime support libraries (32-bit)
106749-04	SCCS and make (32-bit)

TABLE B-3 Patches Installed With Sun Studio 8 Software for Solaris 8 *SPARC Platform Edition*

Patch Identification Number	Patch Description
109147-27	Linker (32-bit)
108434-13 (requires 109147-07)	Solaris 8 C++ runtime support libraries (32-bit)
108435-13 (requires 108434-13)	Solaris 8 C++ runtime support libraries (64-bit)
111697-04	SCCS and make
114802-02	Assembler

TABLE B-4 Patches Installed With Sun Studio 8 Software for Solaris 8 *x86 Platform Edition*

Patch Identification Number	Patch Description
109148-27	Linker (32-bit)
108436-11	Solaris 8 C++ runtime support libraries (32-bit)
111701-04	SCCS and make (32-bit)

TABLE B-5 Patches Installed With Sun Studio 8 Software for Solaris 9 *SPARC Platform Edition*

Patch Identification Number	Patch Description
111711-06	Solaris 9 C++ runtime support libraries (32-bit)

TABLE B-5 Patches Installed With Sun Studio 8 Software for Solaris 9 *SPARC Platform Edition*

Patch Identification Number	Patch Description
111712-06 (requires 111711-06)	Solaris 9 C++ runtime support libraries (64-bit)
111703-03	SCCS and make (32-bit)
112963-10	Linker (32-bit)

TABLE B-6 Patches Installed With Sun Studio 8 Software for Solaris 9 *x86 Platform Edition*

Patch Identification Number	Patch Description
111713-04	Solaris 9 C++ runtime support libraries (32-bit)
113986-06	Linker (32-bit)
115114-01	Assembler

J2SE Technology Required Patch Identification Numbers and Descriptions

Java™ 2, Standard Edition (J2SE) technology required patches are provided in the J2SE installer for Sun Studio 8 software. These patches are required for the proper operation of the J2SE technology with the Solaris Operating System (OS). This appendix lists the Solaris OS patches that are included with this release. These patches are installed automatically unless you change the default selection on the Select Components page during the J2SE technology installation process.

TABLE C-1 lists the patch identification numbers and descriptions for the Solaris 7 OS (*SPARC® Platform Edition*).

TABLE C-2 lists the patch identification numbers and descriptions for the Solaris 7 OS (*x86 Platform Edition*).

TABLE C-3 lists the patch identification numbers and descriptions for the Solaris 8 OS (*SPARC Platform Edition*).

TABLE C-4 lists the patch identification numbers and descriptions for the Solaris 8 OS (*x86 Platform Edition*).

TABLE C-5 lists the patch identification numbers and descriptions for Solaris 9 OS (*SPARC Platform Edition*).

TABLE C-6 lists the patch identification numbers and descriptions for Solaris 9 OS (*x86 Platform Edition*).

TABLE C-1 Patches Installed With the J2SE Technology for Solaris 7 <i>SPARC Platform Edition</i>	
Patch Identification Number	Patch Description
107544-03	/usr/lib/fs/ufs/fsck
106950-24	Linker
106327-20	Shared library for C++ (32-bit)

TABLE C-1 Patches Installed With the J2SE Technology for Solaris 7 *SPARC Platform Edition*

Patch Identification Number	Patch Description
106300-21	Shared library for C++ (64-bit)
108376-44	OpenWindows 3.6.1: Xsun
107656-11	OpenWindows 3.6.1 libXt
107702-12	CDE: 1.3 dtsession
108374-07	CDE: 1.3 libDtWidget
107226-19	CDE: 1.3 dtwm
107081-54	Motif 1.2.7 and 2.1.1: Runtime library
107636-10	X Input & Output Method
107153-01	There are three characters missed in zh.GBK songti.ttf
107834-04	dkio.h & commands.h
106541-27	Kernel Update
106980-23	libthread

TABLE C-2 Patches Installed With the J2SE Technology for Solaris 7 *x86 Platform Edition*

Patch Identification Number	Patch Description
107545-03	/usr/lib/fs/ufs/fsck
106951-24	Linker
106328-18	Shared library for C++
108377-39	OpenWindows 3.6.1_x86: Xsun
107657-09	OpenWindows 3.6.1_x86: ERC X11R6.4 extension
107703-12	CDE 1.3_x86: dtsession
108375-07	CDE 1.3_x86: libDtWidget
107227-19	CDE 1.3_x86: dtwm
107082-54	Motif 1.2.7_x86 and 2.1.1_x86: Runtime library
107637-10	X Input & Output Method
107152-01	There are three characters missed in zh.GBK songti.ttf
114286-01	nei bug fixes
106542-27	Kernel Update
106981-23	libthread

TABLE C-3 Patches Installed With the J2SE Technology for Solaris 8 *SPARC Platform Edition*

Patch Identification Number	Patch Description
108652-74	X11 6.4.1: Xsun
108921-17	CDE 1.4: dtwm
108940-57	Motif 1.2.7 and 2.1.1: Runtime library
112003-03	Unable to load fontset in 64-bit Solaris 8 iso-1 or iso-15
108773-18	IIIM and X Input & Output Method
111310-01	/usr/lib/libdhcpagent.so.1
112472-01	Font2DTest2 abort when Lucida Sans Thai Typewriter selected
109147-26	Linker
111308-03	/usr/lib/libmtmalloc.so.1
112438-02	/kernel/drv/random
111111-03	/usr/bin/nawk
112396-02	/usr/bin/fgrep
110386-03	RBAC Feature
111023-02	/kernel/fs/mntfs and /kernel/fs/sparcv9/mntfs
108987-13	Patch for patchadd and patchrm
108528-24	kernel update
108989-02	/usr/kernel/sys/acctctl and /usr/kernel/sys/exacctsys
108993-26	LDAP2 client, libc, libthread and libnsl libraries

TABLE C-4 Patches Installed With the J2SE Technology for Solaris 8 *x86 Platform Edition*

Patch Identification Number	Patch Description
108653-63	X11 6.4.1_x86: Xsun
108941-57	Motif 1.2.7_x86 and 2.1.1_x86: Runtime library
108922-17	CDE 1.4_x86: dtwm
108774-18	IIIM and X Input & Output Method
111307-05	boot.bin, bootconf.exe, bootenv.rc and nbp
111311-01	/usr/lib/libdhcpagent.so.1
112473-01	Font2DTest2 abort if Lucida Sans Thai Typewriter selected

TABLE C-4 Patches Installed With the J2SE Technology for Solaris 8 *x86 Platform Edition*

Patch Identification Number	Patch Description
112439-02	kernel/drv/random
109148-26	linker
111309-04	/usr/lib/libmtmalloc.so.1
111112-03	/usr/bin/nawk
112397-02	/usr/bin/fgrep
110400-01	RBAC Feature
111024-02	/kernel/fs/mntfs
108988-13	Patch for patchadd and patchrm
108529-24	kernel update
108990-02	acctctl & exacctsys
108994-25	LDAP2 client, libc, libthread, and libnsl libraries

TABLE C-5 Patches Installed With the J2SE Technology for Solaris 9 *SPARC Platform Edition*

Patch Identification Number	Patch Description
113096-03	X11 6.6.1: OWconfig patch
112785-26	X11 6.6.1: Xsun patch

TABLE C-6 Patches Installed With the J2SE Technology for Solaris 9 *x86 Platform Edition*

Patch Identification Number	Patch Description
112786-15	X11 6.6.1_x86: Xsun patch

Version Numbers of Sun Studio 8 Software Components

This appendix provides the version numbers of the components that are included in the Sun Studio 8 software.

TABLE D-1 lists the version numbers of the components.

TABLE D-1 Version Numbers of Components of Sun Studio 8 Software

Component	Version Number
C	5.5
C++	5.5
Fortran 95	7.1
dbx	7.2
dmake	7.4
Locklint	2.4
Performance Analyzer	7.2
Tools.h++	7.1.0
Standard C++ Library	2.1.1
Sun Performance Library	4.1
STLport	4.5.3
X-Designer	7.5
NCT	1.1
Xemacs	21.4.12
gvim	6.2

Glossary

60-day Trial serial number	A number you generate during installation that allows you to use the software for 60 days free of charge.
batch installer	The batch installer is an installer packaged with the product that can install each product component from the command-line with minimal user interaction.
display computer	The computer that displays the installer window or command-line installer. For installation using a local display, the display computer and the source computer are the same computer. For installation using a remote display, the display computer and the source computer are different computers.
installation directory	The directory in which you install Sun Studio 8 software products and licenses. The default directory is <code>/opt</code> on the source computer.
Solaris™ JumpStart installation	The Solaris JumpStart™ installation works with the Solaris 9 Operating System (OS) (<i>SPARC® Platform Edition</i>) and the Solaris 9 OS (<i>x86 Platform Edition</i>) to automate the software installation process to install the Sun Studio 8 software on multiple systems.
local display	An installation method where the product CD-ROM or downloaded product software is on the same computer that you use to perform the installation. The source computer runs the installer, and the installer window is displayed on the monitor that is attached to the source computer.
remote display	An installation method where the product CD-ROM or downloaded product software is on a different computer than the installer window or command-line installer. You use the <code>rlogin</code> command to log in to the source computer that contains the product CD-ROM or downloaded files. You set the <code>DISPLAY</code> environment variable to display the installer window on the monitor that is attached to the display computer. The installer runs on the source computer, but the installer window or command-line installer is displayed on the display computer.

permanent serial number	A 26-character number that is provided with the purchased product. You must enter this permanent serial number during installation or enter it by using the <code>snit</code> software.
source computer	The machine that runs the installer. The source computer contains the product CD-ROM or the downloaded product software.
Try and Buy	Sun Studio 8 software that you install and use on a trial basis with the 60-day Trial serial number.

Index

NUMERICS

60-day trial serial number
 generating, 31, 35
 upgrading to permanent license, 27, 31, 35

A

accessible documentation, 12

B

batch
 command options, 35
 installation, 34

D

display
 local, 19, 87
 remote, 19, 87
 remote display with NFS-mounted
 filesystem, 20
display computer, 87
documentation index, 11
documentation, accessing, 11 to 12, ?? to 13

E

environment variables

changing, 38
MANPATH, 40
PATH, 39

I

IDE
 starting, 43
installation
 batch installer, 34
 CD-ROM, 25
 command-line, 32
 directory, 87
 failed, identifying and fixing, 57
 graphical user interface, 28
 in directory reached by symbolic link, 55
 JumpStart, 36
 overview, 16
 remote display, 19
 remote display with NFS-mounted
 filesystem, 20

J

JumpStart installation, 36

L

license file, displaying contents of, 27
local display, 19, 87

log files, viewing, 59

M

metacenter information, 65

N

NFS-mounted filesystem
remote display installation with, 20
write permission, 61

P

package component information, 65
patch identifications and descriptions, 77, 81
productregistry file, corrupted, 58

R

Registration Wizard
using, 44
remote display, 19, 87
requirements, system, 17

S

serial number
60-day trial serial number, 87
finding lost, 60
generating 60-day trial, 31, 35
installing, 31, 35
locating, 21
permanent, 88
upgrading from a 60-day trial serial number, 30
Serial Number Installation Tool (snit)
finding installed serial number, 60
using to upgrade from 60-day trial to permanent
license, 27
viewing `serial.dat` file, 60
serial number, displaying contents of, 38, 59
Setup Wizard
using, 44

shell prompts, 10
Solaris Product Registry tool, 57
Solaris versions supported, 17
source computer, 88
swap space
adding, 18
checking, 17
system requirements, 17

T

ToolTalk software session, initializing, 61
typographic conventions, 9

U

uninstall file names, 50
uninstallation
command-line, 52
failed, fixing, 57
graphical user interface, 50
upgrading from a 60-day trial serial number, 27, 35

V

version
of components, 85