

HP OpenVMS Migration Software for Alpha to Integrity Servers

Installation Guide

February 2005

This document describes how to install the HP OpenVMS Migration Software for Alpha to Integrity Servers for OpenVMS using the POLYCENTER Software Installation utility.

Revision/Update Information:	This is a new manual.
Software Version:	OpenVMS Migration Software for Alpha to Integrity Servers Version 1.0
Operating System and Version:	OpenVMS Alpha Version 7.3 and higher OpenVMS I64 Version 8.2 and higher

Hewlett-Packard Company
Palo Alto, California

© Copyright 2005 Hewlett-Packard Development Company, L.P.

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

The information contained herein is subject to change without notice. The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

Intel and Itanium are trademarks or registered trademarks of Intel Corporation or its subsidiaries in the United States and other countries.

PostScript is a registered trademark of Adobe Systems Incorporated.

UNIX is a registered trademark of The Open Group.

Microsoft is a registered trademark of the Microsoft Corporation.

Printed in the US

Installing the HP OMSAI Layered Product

1.1 Installation Requirements

Before you install the Migration Software for Alpha to Integrity Servers (OMSAI) software, ensure that you meet the following installation requirements:

- Operating system—OpenVMS Alpha Version 7.3 or higher
- Free disk space—10674 blocks

1.2 Before You Run the Installation Procedure

In addition, you should deinstall previous versions of Binary Translator for OpenVMS before you install the new version. For deinstallation information, see Section 1.3.2.

1.3 Installing the Software

To start the installation procedure, follow these steps:

1. Run the installation procedure:

```
$ PROD INSTALL MSAI
```

```
The following product has been selected:
```

```
HP AXPVMS MSAI V1.0                      Layered Product
```

```
Do you want to continue? [YES]
```

```
Configuration phase starting ...
```

```
You will be asked to choose options, if any, for each selected product and for any product
```

```
HP AXPVMS MSAI V1.0: HP OpenVMS Migration Software for Alpha to Integrity Servers
```

```
Do you want the defaults for all options? [YES]
```

```
Do you want to review the options? [NO]
```

```
Execution phase starting ...
```

```
The following product will be installed to destination:
```

```
HP AXPVMS MSAI V1.0                      DISK$V82SYS:[VMS$COMMON.]
```

```
Portion done: 0%...70%...80%...90%...100%
```

```
The following product has been installed:
```

```
HP AXPVMS MSAI V1.0                      Layered Product
```

```
HP AXPVMS MSAI V1.0: HP OpenVMS Migration Software for Alpha to Integrity Servers
```

```
HP OpenVMS Migration Software for Alpha to Integrity Servers is installed successfully
```

```
$
```

Note

In case there are multiple PCSI kits in the start location, you will be asked to select the appropriate product to install. You should select HP-

Installing the HP OMSAI Layered Product

1.3 Installing the Software

AXPVMS-MSAI-V0100-1.PCSI\$COMPRESSED;1 for OpenVMS Alpha or
HP-I64VMS-MSAI-V0100-1.PCSI\$COMPRESSED;1 for OpenVMS I64, or
a more current version number of the product if one exists."

2. To see a list of the files installed, issue the following command:

```
$> PRODUCT LIST
```

1.3.1 Post Installation Tasks

When installing OMSAI for the first time on your system, a new command AEST is added to DCL. You must log out and then back in to make the AEST command available in the updated DCLTABLES.EXE file.

1.3.2 Deinstalling

To deinstall the Binary Translator, enter the following command:

```
$ PRODUCT REMOVE
_Product name (* to show list): *

 1 - CPQ AXPVMS CDSA V2.1-331          Layered Product
 2 - DEC AXPVMS DECNET_OSI V8.2        Layered Product
 3 - DEC AXPVMS DWMOTIF V1.5           Layered Product
 4 - DEC AXPVMS OPENVMS V8.2           Platform (product suite)
 5 - DEC AXPVMS TCPIP V5.5-11          Layered Product
 6 - DEC AXPVMS VMS V8.2               Operating System
 7 - HP AXPVMS AVAIL_MAN_BASE V8.2     Layered Product
 8 - HP AXPVMS KERBEROS V2.1-72        Layered Product
 9 - HP AXPVMS MSAI V1.0               Layered Product
10 - HP AXPVMS SSL T1.2                Layered Product
11 - HP AXPVMS TDC_RT V2.1-69          Layered Product
12 - JFP AXPVMS LIBBZ2 V1.0-2          Layered Product
13 - JFP AXPVMS ZLIB V1.1-4            Layered Product
14 - QTV AXPVMS PYTHON X2.3-3          Layered Product
15 - All products listed above
? - Help
E - Exit

Choose one or more items from the menu: 9
The following product has been selected:
  HP AXPVMS MSAI V1.0                  Layered Product

Do you want to continue? [YES]
The following product will be removed from destination:
  HP AXPVMS MSAI V1.0                  DISK$V82SYS:[VMS$COMMON.]
Portion done: 0%...10%...20%...30%...40%...50%...60%...70%...80%...100%
The following product has been removed:
  HP AXPVMS MSAI V1.0                  Layered Product
$
```

1.4 Files Installed During Installation

The installation procedure installs the following files on your system:

```
[SYSEXEC]AEST$MAIN.EXE
[SYSHLP]AEST$RELEASE_NOTES.TXT
[SYSLIB]DECC$SHR.AIIF
[SYSLIB]LIBOTS.AIIF
[SYSLIB]LIBRTL.AIIF
```

Installing the HP OMSAI Layered Product

1.4 Files Installed During Installation

[SYSLIB]PTHREAD\$RTL.AIIF
[SYSLIB]SORTSHR_TV.AIIF
[SYSLIB]SYS\$BASE_IMAGE.AIIF
[SYSLIB]SYS\$PUBLIC_VECTORS.AIIF
[SYSLIB]TIE\$SHARE.AIIF

1.5 Files Installed During Installation

The installation procedure updates the following files:

[SYSLIB]DCLTABLES.EXE
[SYSHLP]HELPLIB.HLB